# Guide to Securing Microsoft Windows 2000<sup>®</sup> Group Policy: Security Configuration Tool Set

### Network Security Evaluations and Tools Division of the Systems and Network Attack Center (SNAC)

Author: Julie M. Haney



Updated: July 22, 2002 Version 1.1.1

National Security Agency 9800 Savage Rd. Suite 6704 Ft. Meade, MD 20755-6704

W2KGuides@nsa.gov

### Change Control

Version	Date	Details
1.1	22 Jan. 2002	Added this change control section to track version modifications.
		On pp. 19 and 23, removed references to a "companion CD."
		In Chapter 2, renamed the section "Undoing Security Changes" to "Before Making Security Changes" and moved the section to before the "Checklist for Applying the Recommendations in this Guide" section. In this same section changed "(described later)" to "(described in Chapter 10)."
		On page 23, added the line "ENPASFLT.DLL is available to U.S. government agencies only" under the "Passwords must meet complexity requirements" table entry.
		On page 25 under the Account Lockout Policy section, changed "thousands of well-known passwords are tried" to "thousands of words are tried."
		On page 26, changed "Maximum lifetime for user ticket removal" to "Maximum lifetime for user ticket renewal."
		On page 30, added the "ENTERPRISE DOMAIN CONTROLLERS" group to the "Access this computer from network" user right.
		On page 37, under the table entry for "Allow Server Operators to schedule tasks," corrected the registry entry to be HKLM\System\CurrentControlSet\Control\Lsa\SubmitControl= 0.
		On page 54, under the Maximum log size table entry, changed the last sentence in the note to read "This ensures that the system will still halt if the event log exceeds 4 GB, even if there is space on the hard drive."
		On page 84, moved the incorrect entry for %SystemRoot%\Program Files\Resource Pro Kit to page 80, %ProgramFiles%\Resource Pro Kit.
1.1.1	22 July 2002	On page 41, under the" LAN Manager authentication leve" entry, added "Send NTLMv2 response only – System will still accept LM and NTLM."
		On page 48, under the "Send unencrypted password to connect to third- party SMB servers" entry, corrected the registry path to be HKLM\System\CurrentControlSet\Services\LanmanWorkstation\Parameters\ EnablePlainTextPassword = 0
		On page 70, corrected the security setting for \MACHINE\SYSTEM\CurrentControlSet\Control\Wmi\Security to be Full Control for the Administrators group.
		On page 71, corrected the security setting for USERS\.DEFAULT to read Users instead of Authenticated Users.
		On page 80, changed the description of %SystemDirectory%\rcp.exe to read "Remote copy command."

#### Disclaimer

SOFTWARE IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. IN NO EVENT SHALL THE NATIONAL SECURITY AGENCY OR ANY AGENT OR REPRESENTATIVE THEREOF BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION), HOWEVER CAUSED UNDER ANY THEORY OF LIABILITY, ARISING IN ANY WAY OUT OF THE USE OF OR INABILITY TO MAKE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This Page Intentionally Left Blank

#### Acknowledgements

The author would like to acknowledge the authors of the "Guide to Implementing Windows NT in Secure Network Environments" and the "Guide to Securing Microsoft Windows NT Networks" versions 2.0, 2.1, and 3.0, 4.0, and 4.1.

The author acknowledges Michael Samsel for his development of the Enhanced Password DLL included with this guide.

The author would also like to thank Paul Bartock, Neal Ziring, Edward Wojciechowski, and Kim Downin, along with the many others involved in reviewing this document. Your comments and suggestions were invaluable.

Some parts of this document were drawn from Microsoft copyright materials with their permission.

#### Trademark Information

Microsoft, MS-DOS, Windows, Windows 2000, Windows NT, Windows 98, Windows 95, Windows for Workgroups, and Windows 3.1 are either registered trademarks or trademarks of Microsoft Corporation in the U.S.A. and other countries.

All other names are registered trademarks or trademarks of their respective companies.

### Table of Contents

Change Control	ii
Disclaimer	iii
Acknowledgements	v
Trademark Information	vi
Table of Contents	vii
Table of Figures	ix
Table of Tables	x
Chapter 1 Important Information on Using this Guide	11
Assumptions	
Warnings to Review Before Using this Guide	11
Conventions and Commonly Used Terms	12
About the Guide to Securing Microsoft Windows 2000: Security Configuration Tool Set	13
Comments	14
Chapter 2 Introduction to the Security Configuration Tool Set	15
Security Configuration Functionality	16
Security Templates	16
Default Security Templates	
Microsoft-provided Templates NSA Security Templates	
Before Making Security Changes	
Checklist for Applying the Recommendations in this Guide	19
Chapter 3 Modifying Account Policy Settings with Security Templates	21
Password Policy	21
Account Lockout Policy	25
Kerberos Policy	25
Chapter 4 Modifying Local Policy Settings with Security Templates	27
Auditing Policy	27
User Rights Assignment	
Security Options	35
Adding an Entry to Security Options	50
Chapter 5 Modifying Event Log Settings with Security Templates	53
Event Log Settings	53

Managing the Event Logs	. 54
Chapter 6 Managing Restricted Groups with Security Templates	. 57
Modifying Restricted Groups via the Security Templates Snap-in	. 57
Chapter 7 Managing System Services with Security Templates	. 59
Modifying System Services via the Security Templates Snap-in	. 59
System Services Security	. 60
Chapter 8 Modifying Registry Security Settings with Security Templates	. 63
Inheritance model	. 63
Registry permissions	. 63
Modifying Registry settings via the Security Templates snap-in	. 65
Recommended Registry Key Permissions	. 67
Chapter 9 Modifying File System Security Settings with Security Templates	. 73
File and folder permissions	. 73
Modifying File System settings via the Security Template snap-in	. 76
Recommended File and Folder Permissions	. 78
Chapter 10 Security Configuration and Analysis	. 87
Loading the Security Configuration and Analysis snap-in into the MMC	. 87
Security Configuration Databases	. 88
Secedit Command Line Options	. 89
Performing a Security Analysis	. 90
Configuring a System	. 92
Appendix A Example Logon Banner	. 95
Appendix B References	. 96

### Table of Figures

Figure 1 Security Templates snap-in	17
Figure 2 Password Policy Recommended Settings	24
Figure 3 Recommended User Rights	29
Figure 4 System Services	
Figure 5 Advanced Registry Permissions Dialog Box	
Figure 6 File/Folder Permission Inheritance Options	79
Figure 7 Configuration File Selection	
Figure 8 Results of a Security Analysis	

### Table of Tables

Table 1 Default Security Configuration Files	18
Table 2 Enhanced Security Configuration Files	
Table 3 Password Policy Options	
Table 4 Account Lockout Options	
Table 5 Kerberos Policy Options	
Table 6 Audit Policy Options	
Table 7 User Rights Options	
Table 8 Security Options	50
Table 9 Domain-wide Security Options	50
Table 10 Event Log Options	54
Table 11 Registry Permissions and Descriptions	64
Table 12 Registry Permission Options	64
Table 13 Recommended Registry Permissions	71
Table 14 File Permissions and Descriptions	74
Table 15 Folder Permissions Options	75
Table 16 File Permissions Options	76
Table 17 Recommended File Permissions	86
Table 18 Secedit Command Line Parameters	90

#### Chapter

### Important Information on Using this Guide

The purpose of this document is to inform the reader about the Windows 2000 Security Configuration Tool Set's capabilities and recommended security settings that can be configured via the tool set. This document represents only a portion of Group Policy security-related issues. Additional security information on Group Policy Objects (GPOs) is addressed in the *Guide to Securing Microsoft Windows 2000 Group Policy*, which should be read prior to reading this document.

Included with this document are four security templates: W2K DC.inf, W2K Workstation.inf, W2K Server.inf, and W2K Domain Policy.inf. The purpose and use of these templates will be discussed later in this document.

This document is intended for Windows 2000 network administrators, but should be read by anyone involved or interested in Windows 2000 or network security.

#### Assumptions

The following essential assumptions have been made to limit the scope of this document:

- □ The network consists only of machines running Microsoft Windows 2000 cleaninstalled machines (i.e., not upgraded).
- The latest Windows 2000 service pack and hotfixes have been installed. For further information on critical Windows 2000 updates, see the Windows Update for Windows 2000 web page <u>http://windowsupdate.microsoft.com</u> or search for security hotfixes by service pack at the Technet Security Bulletin Search <u>http://www.microsoft.com/technet/security/current.asp</u>.
- □ All network machines are Intel-based architecture.
- □ Applications are Windows 2000 compatible.
- Users of this guide have a working knowledge of Windows 2000 installation and basic system administration skills.

#### Warnings to Review Before Using this Guide

The user should read and agree with the following warnings/caveats prior to configuring a network with this guide's recommendations:

- □ Do not attempt to install any of the settings in this guide without first testing in a non-operational environment.
- This document is only a guide containing recommended security settings. It is not meant to replace well-structured policy or sound judgment. Furthermore, this guide does not address site-specific configuration issues. Care must be taken when implementing this guide while using products such as Microsoft Exchange, IIS, and SMS.

- □ The security changes described in this document only apply to **Microsoft Windows 2000** systems and should not be applied to any other Windows 2000 or Windows NT versions or operating systems.
- □ A Windows 2000 system can be severely impaired or disabled with incorrect changes or accidental deletions when using programs (examples: Security Configuration Tool Set, Regedt32.exe, and Regedit.exe) to change the system configuration. Therefore, it is extremely important to test all settings recommended in this guide before installing them on an operational network.
- □ Currently, no Undo function exists for deletions made within the Windows 2000 registry. The registry editor (Regedt32.exe or Regedit.exe) prompts the user to confirm the deletions if **Confirm On Delete** is selected from the options menu. When a registry key is being deleted, the message does not include the name of the key being deleting. Check your selection carefully before proceeding with any deletion.
- □ Care should be taken when applying this document's recommended security settings on Exchange 2000 servers. There will be occasional notes/warnings when settings could affect the operation of Exchange servers, but it is highly recommended that the upcoming NSA Exchange 2000 security guide be reviewed prior to applying the provided recommendations.

#### Conventions and Commonly Used Terms

#### Users and Authenticated Users

For permissions on Windows 2000 workstations and member servers, Microsoft now makes wide use of the Users group. The Users group by default contains the Authenticated Users group and INTERACTIVE user (along with Domain Users for a domain machine). Membership in Users can be controlled by administrators, which is Microsoft's reasoning for using this group in access control lists. Looking at the default security templates for workstations and member servers (see the next chapter for information on these templates), the Users group is used in file and registry permissions as well as user rights assignment.

However, Microsoft uses the built-in Authenticated Users group to assign permissions on domain controllers. Out-of-the-box domain controller security templates replace Users with Authenticated Users.

This guide has chosen to follow Microsoft's convention. No security should be lost if you choose to replace the Users group with the Authenticated Users group on workstations and member servers.

#### System Variables

The following system variables are referenced throughout this document:

- SystemDrive% The drive letter on which Windows 2000 is installed. This is usually C:\.
- %SystemRoot% The folder containing the Windows 2000 operating system files. This is usually %SystemDrive%\winnt.
- **%SystemDirectory%** %SystemRoot%\system32

%ProgramFiles% - Folder in which most applications are installed. This is usually %SystemDrive%\Program Files.

# About the Guide to Securing Microsoft Windows 2000: Security Configuration Tool Set

This document consists of the following chapters:

**Chapter 1, "Important Information on Using this Guide,"** (this chapter) provides important assumptions and warnings to be read prior to using the guide.

**Chapter 2, "Introduction to the Security Configuration Tool Set,**" provides an overview of the Security Configuration Tool Set and its capabilities and describes how to use the Security Templates Microsoft Management Console (MMC) snap-in to implement, edit, and create new security configuration files. This chapter also introduces the security configuration files included with this document and details a checklist for configuring a network using the provided settings.

**Chapter 3, "Modifying Account Policy Settings with Security Templates,**" explains how to set domain wide account policies using the Security Templates snap-in. The section also covers Password Policy, Account Lockout, and Kerberos Policy.

**Chapter 4**, "**Modifying Local Policy Settings with Security Templates**," illustrates how to use the Security Templates snap-in to implement and modify Local Policy settings. Specifically this section describes suggested policies for Auditing, User Rights, and Security Attributes.

**Chapter 5, "Modifying Event Log Settings with Security Templates,"** explains how to capture, view, and store the critical events that have occurred on the network by modify the Event Log Settings. Also included in this section is management of Event Logs.

**Chapter 6, "Managing Restricted Groups with Security Templates,"** discusses how to manage the membership of sensitive groups using the Restricted Groups option.

**Chapter 7, "Managing System Services with Security Templates,"** illustrates how to manage System Service settings such as Startup Modes and Access Control Lists using the Security Templates snap-in. This section also describes how settings are established that can control which users and/or groups can read and execute, write to, delete, start, pause, or stop a service.

**Chapter 8, "Modifying Registry Security Services with Security Templates,"** discusses how to configure access control lists for Registry Keys. Also discussed is how to implement adequate security in a Windows 2000 environment, by modifying registry keys and their associated permissions must be changed.

**Chapter 9, "Modifying File System Security Settings with Security Templates,"** steps the reader through the actions required to modify file and folder permissions using the Security Templates snap-in. Additionally, this section outlines recommended file and folder permission settings.

**Chapter 10, "Security Configuration and Analysis,"** explains how to perform security analysis and configuration via the Security Configuration and Analysis snap-in or the command line program, once the appropriate configuration file(s) have been modified.

### Comments

As this document is a work in progress, comments, suggestions, questions, and bug reports are welcomed and encouraged. Send an email to <u>W2KComments@dewnet.ncsc.mil</u> describing the issue in detail. In order to allow ample time to research problems, email is preferred to phone calls.

Chapter

2

# Introduction to the Security Configuration Tool Set

Windows 2000 includes support for the Security Configuration Tool Set. The tool set allows system administrators to consolidate many security-related system settings into a single configuration file (called a template or inf file in this guide because of the file extension .inf). It is possible to layer security configuration files to adjust for different software applications and security settings. These security settings may then be applied to any number of Windows 2000 machines either as part of a Group Policy Object (GPO) or through local computer configuration.

The Security Configuration Tool Set allows analysis and configuration of the following security areas:

- Account Policies includes Password Policy, Account Lockout Policy, and Kerberos Policy
- Local Policies includes Audit Policy, User Rights Assignment, and Security Options
- Event Log includes settings for the event logs
- **Restricted Groups** includes membership settings for sensitive groups
- System Services includes configurations for system services such as network transport
- Registry includes registry key Discretionary Access Control List (DACL) settings (i.e., registry key permissions)
- File System includes NTFS file and folder DACLs (i.e., file and folder permissions)

Chapters 3 - 9 describe recommended settings and how to customize the templates, and Chapter 10 describes how to conduct a security analysis and configuration.

For more detailed information on the Security Configuration Tool Set, refer to the *Step by Step Guide to Using the Security Configuration Toolset* <u>http://www.microsoft.com/windows2000/techinfo/planning/security/secconfsteps.asp</u>.

#### Security Configuration Functionality

The Security Configuration Tool Set supports both a graphical user interface (GUI) and a command line tool.

#### The Security Configuration GUI

The graphical user interface is provided via the Microsoft Management Console (MMC). The MMC is a container for administrative tools and is used extensively in Windows 2000. Tools are imported into the MMC via "snap-ins."

In actuality, the Security Configuration Tool Set consists of two MMC snap-ins: Security Templates and Security Configuration and Analysis. Both snap-ins will be discussed in greater detail in this chapter and Chapter 10, respectively.

The security configuration GUI allows an administrator to:

- Create and/or edit security configuration files
- Perform a security analysis
- Graphically review the analysis results
- Apply a security configuration to a system

The GUI provides different colors, fonts, and icons to highlight the differences between the baseline information and the actual system settings. When an analysis or configuration is performed, all security areas within a security template are included in the analysis.

#### The Security Configuration Command Line Tool

The security configuration command line tool (secedit.exe) is all that is needed to:

- Perform a security analysis
- Apply a security configuration to a Windows 2000 system

The command line option allows for analysis of individual security areas versus the entire configuration file. Also, analysis results can be redirected to a file for review at a later time. The command line tool is also useful for applying predefined configuration files to many systems using distributed systems management tools.

#### Security Templates

Security templates are files that contain a set of security configurations. Templates provide an easy way to standardize security across a platform or domain. They may be applied to Windows 2000 computers either by being imported into a Group Policy Object, or by being directly applied to the local computer policy.


This section provides a general overview of the Security Templates snap-in and discusses the security configuration files included with the tool.

#### Loading the Security Templates Snap-in into the MMC

The Security Templates snap-in must be loaded into the Microsoft Management Console (MMC). The MMC is loaded by default on Windows 2000 systems. To load the Security Templates snap-in:

- □ Run the Microsoft Management Console (mmc.exe)
- $\Box \quad \text{Select Console} \rightarrow \text{Add/Remove Snap-in}$
- □ Click Add
- □ Select Security Templates
- □ Click Add
- Click Close
- □ Click OK

Figure 1 shows the Security Templates snap-in loaded into the MMC.



#### Figure 1 Security Templates snap-in

To avoid having to reload the snap-in every time the MMC is exited and reopened, save the current console settings by performing the following:

□ In the Console menu, select Save. By default, the file will be saved in the Administrative Tools menu of the currently logged-on user.

- □ Enter the file name under which the current console settings will be saved
- Click Save

From then on, the console can be accessed from Start  $\rightarrow$  Program Files  $\rightarrow$  Administrative Tools.

#### Security Configuration Files

This section describes the default and NSA security templates available for the Security Templates snap-in.

#### Default Security Templates

There are several security template files that contain the default security settings applied to a clean-install (non-upgraded) Windows 2000 machine. These files reside in the <code>%SystemRoot%\inf</code> folder. Table 1 shows a list of the default security templates.

The default security templates are especially useful when wanting to return the system to its original state or when converting from a FAT or FAT32 file system to NTFS. When a conversion is made, the default settings on the file system default to the "Everyone" group having full control over all files and folders. To obtain the file system security settings that would have been present if NTFS had been the original file system, apply the File System portion of the appropriate default security template. See Chapter 10 for more information on running secedit.exe and specifying that only the file system be configured.

File Name	Platform
Defltdc.inf	Windows 2000 Server/Advanced Server Domain Controller
Defltsv.inf	Windows 2000 Server/Advanced Server
Defltwk.inf	Windows 2000 Professional

#### Table 1 Default Security Configuration Files

The template actually applied to a machine out-of-the-box is stored in %SystemRoot%\security\templates as setup security.inf. Domain controllers will, in addition, be configured with the settings in a template called DC security.inf.

#### Microsoft-provided Templates

Within the Security Templates snap-in, Microsoft provides several templates addressing varying levels of security. Among these are <code>basicwk.inf</code>, <code>basicdc.inf</code>, <code>basicdc.inf</code>, <code>basicsv.inf</code>, <code>securedc.inf</code>, <code>securews.inf</code>, <code>hisecdc.inf</code>, and <code>hisecws.inf</code>. Since this guide's recommended security settings are addressed in the NSA-provided templates (see section below), the details of the Microsoft templates will not be discussed here.

#### NSA Security Templates

This document also includes a set of security configuration files that comply with the recommendations found in this manual. Refer to **Table 2** below in order to choose the file(s) appropriate for your system(s).

File Name	Platform	Description
W2K DC.inf	Windows 2000 Server/Advanced Server Domain Controller	Enhanced security settings for Windows 2000 domain controllers
W2K Workstation.inf	Windows 2000 Professional	Enhanced security settings for Windows 2000 workstations
W2K Server.inf	Windows 2000 Server/Advanced Server	Enhanced security settings for Windows 2000 member or standalone servers
W2K Domain Policy	Windows 2000 domain	Enhanced account policy settings to be applied in a domain-level Group Policy Object

#### **Table 2 Enhanced Security Configuration Files**

#### Before Making Security Changes

If problems arise after applying the security templates to a system, troubleshooting may be difficult if many settings were applied at once. First and foremost, try the settings out in a test environment before applying to an operational network. Also try configuring one section of the templates at a time via the command line secedit.exe tool (described in Chapter 10) or by isolating specific sections in a separate inf file. This method will allow you to apply one part of the templates (e.g. Account Policy or File System) and then test the system for problems before moving onto the next section.

The only sure-fire way to restore a system to its original configuration is via a **backup**. The setup security.inf file (mentioned earlier in this chapter) can be used to reset most settings to their default (out-of-the-box) values. However, any settings specified as "Not Defined" in the default template will not change the values configured by the NSA templates.

#### Checklist for Applying the Recommendations in this Guide

This section provides a general checklist of steps to be performed when customizing the security templates included in this document.

- Review and understand the warnings in Chapter 1. It is NOT recommended that the NSA-provided templates be applied blindly without thoroughly reviewing the settings in Chapters 3-9.
- Backup your system, especially if it is a server or domain controller. Backups are the only sure-fire way to restore your system if security configurations break something.
- Download the appropriate configuration files (the .INF files available on the website www.nsa.gov) to the template directory (%Systemroot%\Security\Templates). Review Table 2 to determine the necessary template file(s).
- □ It is suggested that you make copies of the template files under different names if you plan to perform modifications to the recommended settings. You can do this

prior to opening the files in the MMC, or by performing a Save As after making modifications to the templates (see the above section on Editing Security Configuration Files).

- Several new security options have been added to the NSA templates. To make these options available, download the NSA sceregvl.inf file from the website into the %SystemRoot%\inf folder. You should rename the original copy of sceregvl.inf prior to copying the NSA-provided file in case you need to revert back to original configurations.
- □ To register the new security options, from the command prompt run regsvr32 scecli.dll. The end of Chapter 4 discusses how other security options can be added to the templates.
- Review the recommended security settings in Chapters 3 9. Via the Security Templates MMC snap-in, modify the template files according to your network's needs. Pay close attention to any notes or warnings associated with the settings. To modify the templates:
  - U Within the MMC, double-click on the Security Templates node in the left pane
  - □ Double-click the default configuration file directory (%Systemroot%\Security\Templates). A list of available configuration files is revealed.



NOTE: Template files from other directories may be loaded by right-clicking on Security Templates and choosing the New Template Search Path option.

- Double-click on a specific configuration file
- Double-click on a specific security area
- Double click on a security object in the right pane
- □ Customize the security setting for your environment
- □ To save the customized configuration file under a new file name (to avoid writing over the provided templates), right-click on the file in the left pane and select Save As, specifying a new name for the modified template
- Several security settings are recommended, but not defined in the templates because they are environment specific. You will have to decide on the values for the configurations. Among these settings are the following security options presented in Chapter 4:
  - Message text for users attempting to log on
  - Message title for users attempting to log on
  - Rename Administrator account
  - Rename Guest account
- Once the templates have been customized to your network environment and saved, apply the templates. If the template will be applied locally, see Chapter 10 for information on configuration options via the Security Configuration and Analysis snap-in or the secedit.exe command line tool. If the template will be imported into a Group Policy Object, please refer to the *Guide to Securing Microsoft Windows 2000 Group Policy*.

## Modifying Account Policy Settings with Security Templates

A key component of controlling the security in a Windows 2000 domain is the proper setting of account policies. Depending on the type of system (e.g. domain controller, workstation, member server), account policy configuration will impact the network differently. In Windows 2000 domains, account policy is set and enforced in the domain's Group Policy. Attempts to configure domain account policies in other GPOs are ignored. Configuring account policies directly on workstations and member servers only impacts the local password or lockout policy on the machine. To ensure a consistent password and lockout policy throughout the entire domain for both local and domain logons, the same policy should be set on the domain controllers (via the domain GPO), member servers and workstations. See the *Guide to Securing Microsoft Windows 2000 Group Policy* for more information on importing security templates into the appropriate containers.

To view account policy settings of a security template double-click the following in the MMC:

- Security Templates
- □ Default configuration file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- Account Policies



NOTE: After making any modifications to the configuration files make sure the changes are saved, and then test the changes before installing them on an operational network.

#### Password Policy

Before making modifications to the **Account Policy** dialog box, review your organization's written password security policy. The settings made in the **Account Policy** dialog box should comply with the written password policy. Users should read and sign statements acknowledging compliance with the organizational computer policy.

Recommendations for a password policy include:

- Users should never write down passwords
- Passwords should be difficult to guess and include uppercase, lowercase, special (e.g., punctuation and extended character set), and numeric characters

□ Users should not transmit clear-text passwords using any form of electronic communications.

To modify the password policy settings via the Security Templates snap-in, double-click the following path:

**Table 3** lists the recommended password policy settings and **Figure 2** shows thepassword policy as it appears in the MMC.

Password Policy Options	Recommended
	Settings
<b>Enforce password history</b> Prevents users from toggling among their favorite passwords and reduces the chance that a hacker/password cracker will discover passwords. If this option is set to 0, users can revert immediately back to a password that they previously used. Allowable values range from 0 (do not keep password history) to 24 passwords remembered.	24 Passwords
Maximum Password Age The period of time that a user is allowed to have a password before being required to change it. Allowable values include 0 (password never expires) or between 1 and 999 days. The maximum password age may be set to less than 90 days in more secure environments.	90 days
<b>Minimum Password Age</b> The minimum password age setting specifies how long a user must wait after changing a password before changing it again. By default, users can change their passwords at any time. Therefore, a user could change their password, then immediately change it back to what it was before. Allowable values are 0 (password can be changed immediately) or between 1 and 998 days.	1 Day
Minimum Password Length         Blank passwords and shorter-length passwords are easily guessed by password cracking tools. To lessen the chances of a password being cracked, passwords should be longer in length. Allowable values for this option are 0 (no password required) or between 1 and 14 characters.         NOTE:       In actuality, Windows 2000 supports passwords up to 127 characters long. However, the security templates interface will not allow setting of minimum password length to be greater than 14. Also, if a network contains Windows 9x computers, the maximum password length cannot exceed 14 characters.         NOTE:       It is recommended that privileged users (such as administrators) have passwords longer than 12 characters if possible.	12 Characters

Password Policy Options	Recommended
	Settings
Passwords must meet complexity requirements	Enabled
Enforces strong password requirements for all users by use of a dynamic	
link library called passfilt.dll. Stronger passwords provide some	
measure of defense against password guessing and dictionary attacks	
launched by outside intruders. Passwords must contain characters from 3	
of 4 classes: upper case letters, lower case letters, numbers, and special	
characters (e.g., punctuation marks). Also, passwords cannot be the same	
as the user's logon name.	
Complexity requirements will take effect the next time a user changes his	
password. Already-existing passwords will not be affected.	
filter, ENPASFLT.DLL, that can be used in place of the Microsoft-provided PASSFILT.DLL. ENPASFLT.DLL is available to U.S. government agencies only. This password filter enforces passwords of at least 8 characters in length containing all 4 classes of characters. Additionally, the use of the user logon name or full name as a password is not permitted. See the ENPASFLT documentation for installation procedures. If using ENPASFLT instead of PASSFILT, you may want to set this option to "Disabled" to avoid conflicts between the two DLLs.	
Store password using reversible encryption for all users in the	Disabled
domain	
Determines whether user passwords will be stored using a two-way hash.	
This option exists to provide password information to certain applications.	
However, storing passwords with reversible encryption is similar to storing clear-text passwords and should NOT be permitted.	

**Table 3 Password Policy Options** 




Figure 2 Password Policy Recommended Settings

#### Account Lockout Policy

Account lockout is recommended after three invalid logon attempts. This setting will slow down a dictionary attack in which thousands of words are tried. If the account is locked out after each invalid attempt to logon, the attacker must wait until the account is enabled again. If an account is locked out, the administrator can reset it using **Active Directory Users and Computers** for domain accounts or **Computer Management** for local accounts instead of waiting the allotted lockout duration.

To modify the account lockout policy settings via the Security Templates snap-in, doubleclick the following path:

Account Policies -> Account Lockout Policy -> specific option to view or edit settings

**Table 4** lists the recommended account lockout policy settings.

Account Lockout Policy Options	Recommended Settings
Account lockout duration Sets the number of minutes an account will be locked out. Allowable values are 0 (account is lockout out until administrator unlocks it) or between 1 and 99999 minutes. WARNING: Setting this value to 0 (until administrator unlocks) may allow a potential denial of service attack. It is important to note that the built-in Administrator account cannot be locked out.	15 minutes
Account lockout threshold Prevents brute-force password cracking/guessing attacks on the system. This option specifies the number of invalid logon attempts that can be made before an account is locked out. Allowable values range from 0 (account will not lockout) to 999 attempts. NOTE: Failed logons on machines that have been locked via CTRL-ALT-DEL or a password- protected screen saver do not count as failed attempts.	3 Invalid logon attempts
Reset account lockout counter after Sets the number of minutes until the invalid logon count is reset. Allowable values range from 1 to 99999 minutes.	15 minutes

#### Table 4 Account Lockout Options

#### **Kerberos Policy**

Kerberos is the default authentication method used in Windows 2000 Active Directory. Since Active Directory is necessary for Kerberos authentication, the Kerberos policy only has significance for the Windows 2000 domain Group Policy Object. Therefore, for the standalone workstation and server configurations that this document addresses, the Kerberos policies will not be defined.

To modify Kerberos settings via the Security Templates snap-in, double-click the following path:

 Table 5 lists the Kerberos Policy options that should be applied at the domain group policy level (in the provided Domain Policy.inf template).

Kerberos Policy Options	Recommended Settings
<b>Enforce user logon restrictions</b> Forces the Key Distribution Center (KDC) to check if a user requesting a service ticket has either the "Log on locally" (for local machine service access) or "Access this computer from the network" user right on the machine running the requested service. If the user does not have the appropriate user right, a service ticket will not be issued. Enabling this option provides increased security, but may slow network access to servers.	Enabled
Maximum lifetime for service ticket Determines the number of minutes a Kerberos service ticket is valid. Values must be between 10 minutes and the setting for "Maximum lifetime for user ticket." This value is set to 600 minutes in the default domain GPO. NOTE: Expired service tickets are only renewed when making a new connection to a server. If a ticket expires during an established session, the session is not interrupted.	600 minutes
Maximum lifetime for user ticket Determines the number of hours a Kerberos ticket-granting ticket (TGT) is valid. Upon expiration of the TGT, a new one must be obtained or the old one renewed. This value is set to 10 hours in the default domain GPO.	10 hours
Maximum lifetime for user ticket renewal Sets the maximum number of days that a user's TGT can be renewed. This value is set to 7 days in the default domain GPO.	7 days
Maximum tolerance for computer clock synchronization Sets the maximum number of minutes by which the KDC and client machine's clocks can differ. Kerberos makes use of time stamps to determine authenticity of requests and aid in preventing replay attacks. Therefore, it is important that KDC and client clocks remain synchronized as closely as possible. This value is set to 5 minutes in the default domain GPO.	5 minutes

**Table 5 Kerberos Policy Options** 



4

# Modifying Local Policy Settings with Security Templates

The Local Policies section in the Security Templates snap-in includes Audit Policy, User Rights Assignment, and Security Options. To view local policy settings of a security template, double-click the following in the MMC:

- □ Security Templates
- Default configuration file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- □ Local Policies



NOTE: After making any modifications to the configuration files make sure the changes are saved and then test the changes before installing them on an operational network.

#### Auditing Policy

Auditing is critical to maintaining the security of the domain. On Windows 2000 systems, auditing is not enabled by default. Each Windows 2000 system includes auditing capabilities that collect information about individual system usage. The logs collect information on applications, system, and security events. Each event that is audited in an audit policy is written to the security event log, which can be viewed with the Event Viewer.



WARNING: Auditing can consume a large amount of processor time and disk space. It is highly recommended that administrators check, save, and clear audit logs daily/weekly to reduce the chances of system degradation or save audit logs to a separate machine. It is also recommended that logs be kept on a separate partition.

To modify the audit policy settings via the Security Templates snap-in, double-click the following path:

Local Policies  $\rightarrow$  Audit Policy  $\rightarrow$  specific option to view or edit

**Table 6** lists recommended Audit Policy Settings for domain controllers, member servers, and workstations.



NOTE: Auditing is important on all domain machines, workstations and servers alike. However, if operational constraints do not make auditing on all machines possible, at a minimum, auditing should be enabled on all servers.

Audit Policy Options	Recommended
5 1	Settings
Audit account logon events	Success, Failure
Tracks user logon events on other computers in which the local computer was	Ouccess, Failure
used to authenticate the account.	
Audit account management	Success, Failure
Tracks changes to the Security Account database (i.e., when accounts are	
created, changed, or deleted).	
Audit directory service access	No auditing
Audits users' access to Active Directory objects that have their system access	(workstations and
control list (SACL) defined. This option is similar to Audit Object Access except that it only applies to Active Directory objects and not files and registry objects.	member servers)
Since this option only applies to Active Directory objects and hot mes and registry objects.	Failure (domain
workstations and member servers.	controllers)
	oonalohoio)
Audit logon events	Success, Failure
Tracks users who have logged on or off, or made a network connection. Also	,
records the type of logon requested (interactive, network, or service). This option	
differs from "Audit Account Logon Events" in that it records where the logon	
occurred versus where the logged-on account lives.	
Track failures to record possible unauthorized attempts to break into the system.	
NOTE: The auditing of successful and failed logon events	
generates a large amount of data. Network, service, and user	
logons are all recorded. Auditing of success events is	
important for tracking users logged on during potential	
attacks. However, if log space is at a premium, at a minimum, failure of logon events should be recorded.	
	Failure
Audit object access Tracks unsuccessful attempts to access objects (e.g., directories, files, printers).	Fallure
Individual object auditing is not automatic and must be enabled in the object's	
properties.	
Audit policy change	Success, Failure
Tracks changes in security policy, such as assignment of privileges or changes in	
the audit policy.	
Audit privilege use	Failure
Tracks unsuccessful attempts to use privileges. Privileges indicate rights	
assigned to Administrators or other power users. Tracks all user rights except	
Bypass Traverse Checking, Debug Programs, Create a Token Object, Replace	
Process Level Token, Generate Security Audits, Back Up Files and Directories, and Restore Files and Directories.	
<b>NOTE: The</b> Audit use of all user rights including Backup	
and Restore setting under Security Options will audit those	
user rights excluded here.	
	No Audition
Audit process tracking Detailed tracking information for events such as program activation and exits.	No Auditing
This option is useful to record specific events in detail if your system is believed	
to be under attack.	
	0
Audit system events	Success. Failure
Audit system events	Success, Failure
	Success, Failure

**Table 6 Audit Policy Options** 

#### User Rights Assignment

User rights are allowable actions that can be assigned to users or groups to supplement built-in abilities. Careful allocation of user rights can significantly strengthen the security of a Windows 2000 system. The recommended user rights are listed and described in **Figure 3** and **Table 7**. Advanced user rights are assigned to Administrators or other trusted users who are allowed to run administrative utilities, install service packs, create printers, and install device drivers. If resources are available, it is recommended assigning these duties to several trusted users. Administrators are not explicitly listed for rights they implicitly have.

ĥ	Ŋ	

NOTE: Based on network policies, some users/groups may need to be added or deleted from the recommended user rights

To modify the user rights settings via the Security Templates snap-in, double-click the following path:

- □ Local Policies → User Rights Assignment
- **D** Right-click on the desired Attribute in the right frame
- □ Select Security
- $\Box \quad \text{To add a user or group, } Add \rightarrow Select user or group \rightarrow Add \rightarrow OK \rightarrow OK$

Console Window Help		D 🚅 🖬 🔟 💵
	X GL 18	
net   Favorites	Policy A	Computer Setting
Conside Paid Security Templates Conside Paid Security Templates Criterian Desiron Desi	Access the computer from the network     Access the computer from the network     Access part of the operating system     Access the computer from the network     Access to domain     Access to domain     Access to domain     Domain the system tene     Domain the system tene     Domain ten system tene     Domain teness     Domain tenesystem     Domain teness     Domain tenesstenes     Domain teness	Administrations Administrations
	1	

□ To remove a user or group, select user or group  $\rightarrow$  Remove  $\rightarrow$  OK

**Figure 3 Recommended User Rights** 

User Rights	Windows 2000	Windows 2000 Domain
	Workstations	Controllers and Member
		Servers
Access this computer from network	Administrators	Administrators
Allows a user to connect over the network Allows a user to connect over the network to the computer. NOTE: If the system is an IIS 5.0 server, whenever the IIS 5.0 service is stopped and restarted, or the machine is rebooted, the IUSR_ <machine_name> and IWAM_<machine_name> will automatically be assigned this right (although it is not necessary). If the security template is applied via Group Policy, these accounts will be removed from this right when the policy is refreshed. See NSA's "Guide to the Secure Configuration and Administration of Microsoft Internet Information Services 5.0" for information on a workaround for this issue.</machine_name></machine_name>	Users	Authenticated Users (DCs only) ENTERPRISE DOMAIN CONTROLLERS (DCs only) Users (Member Servers only)
Act as part of the operating system	(No one)	(No one)
Allows a process to perform as a secure, trusted		
part of the operating system. Some subsystems		
are granted this right. Add workstations to domain	(No one)	(No one)
Allows a user to add workstations to a particular domain. This right is meaningful only on domain controllers. The Administrators and Account Operators groups have the ability to add workstations to a domain and do not have to be explicitly given this right. NOTE: By default, Authenticated Users are given this right on Domain Controllers. Allowing users to add their own machines to a domain could pose security		
risks. Therefore, it is recommended that the Authenticated Users group not be granted this right.		
Back up files and directories Allows a user to back up files and directories. This right supersedes file and directory permissions.	Administrators	Administrators
NOTE: If the network makes use of the Backup Operators or similar group, also assign this right to that group.		
<b>Bypass traverse checking</b> Allows a user to change directories and access files and subdirectories even if the user has no permission to access parent directories.	Users	Authenticated Users (DCs only) Users (Member Servers only)

Chapter 4 – Modifying Local Policy Settings with Security Templates

User Rights	Windows 2000	Windows 2000 Domain
	Workstations	Controllers and Member
		Servers
Change the system time	A desiriate to re	
<u>Change the system time</u> Allows a user to set the time for the internal clock	Administrators	Administrators
of the computer.		
Create a pagefile	Administrators	Administrators
Allows a user to create new pagefiles for virtual		
memory swapping and change the size of a		
pagefile.		
Create a token object	(No one)	(No one)
Allows a process to create access tokens that can		
be used to access local resources. Only the Local		
Security Authority should be allowed to create this		
object.		
Create permanent shared objects	(No one)	(No one)
Allows a user to create special permanent		
directory objects, such as \\Device, that are used		
within the Windows 2000 object manager.		
Debug programs	(No one)	(No one)
Allows a user to debug various low-level objects		
such as threads.		
NOTE: Software developere		
NOTE: Software developers working on the system may		
need this right. Assign the		
right to developer		
users/groups only when		
necessary.		
Deny access to this computer from the	(No one)	(No one)
<u>network</u>		
Prevents specific users and/or groups from		
accessing the computer via the network. This		
setting supercedes the "Access this computer		
from the network" setting if an account is subject		
to both policies.		
Deny logon as a batch job	(No one)	(No one)
Prevents specific users and/or groups from		
logging on as a batch job. This setting supercedes the "Logon as a batch job" setting if an account is		
subject to both policies.		
Deny logon as a service	(No one)	(No one)
Prevents specific service accounts from		
registering a process as a service. This setting		
supercedes the "Log on as a service" setting if an		
account is subject to both policies.		
Deny logon locally	(No one)	(No one)
Prevents specific users and/or groups from		(
logging on directly at the computer. This setting		
supercedes the "Log on locally" setting if an		
account is subject to both policies.		
Enable computer and user accounts to be	(No one)	Administrators (domain
trusted for delegation	(,	controllers)
		,
Allows a user to set the "I rusted for Delegation"		1
Allows a user to set the "Trusted for Delegation" setting on a user or computer object. The user		(No one) (member servers)
setting on a user or computer object. The user		(No one) (member servers)
		(No one) (member servers)

Policy Settings with Security	Templates
	Policy Settings with Security
Chapter 4 – Modifving Loca	Chapter 4 – Modifying Local

User Rights	Windows 2000	Windows 2000 Domain
	Workstations	Controllers and Member
		Servers
Force shutdown from a remote system	Administrators	Administrators
Allows a user to shutdown a Windows 2000	Auministrators	Administrators
system remotely over a network.		
Generate security audits	(No one)	(No one)
Allows a process to generate security audit log		
entries.		
Increase quotas	Administrators	Administrators
Allows a user to increase the processor quota		
assigned to a process.		
Increase scheduling priority	Administrators	Administrators
Allows a user to boost the execution priority of a process. This can be performed via the Task		
Manager user interface.		
Load and unload device drivers	Administrators	Administrators
Allows a user to install and remove device drivers.		
This right is necessary for Plug and Play device		
driver installation.		
Lock pages in memory Allows a user to lock pages in memory so they		
cannot be paged out to a backing store such as		
Pagefile.sys.		
	(No one)	(No one)
NOTE: This right is obsolete		
in this version of Windows 2000.		
Log on as a batch job		
Allows a user to log on by means of a batch- queue facility. In Windows 2000, the Task		
Scheduler automatically grants this right as		
necessary.		
NOTE: If the system is an IIS 5.0 server, whenever the IIS		
5.0 service is stopped and		
restarted, or the machine is		
rebooted, the		
IUSR_ <machine_name> and IWAM_<machine_name> will</machine_name></machine_name>		
automatically be assigned	(No one)	(No one)
this right (although it is not		
necessary). If the security template is applied via Group		
Policy, these accounts will be		
removed from this right when		
the policy is refreshed. See		
NSA's "Guide to the Secure Configuration and		
Administration of Microsoft		
Internet Information Services		
5.0" for information on a workaround for this issue.		

Llear Dighte	Windows 2000	Windows 2000 Domain
User Rights		
	Workstations	Controllers and Member
		Servers
Log on as a service Allows a process to register with the system as a service. NOTE: Some applications such as Microsoft Exchange require a service account, which should have this right. Review the users/groups assigned this right on the system PRIOR to applying the security templates in order to determine which assignments are necessary.	(No one)	(No one)
WARNING: The provided template files will remove all users/groups from this right unless you modify the setting.		
Log on locally Allows a user to log on at a system's console. To allow a user to log on locally at a domain controller, this right must be enabled in the Domain Controller group policy object. NOTE: If the system is an IIS 5.0 Server, the IUSR_ <machine_name> and IWAM_<machine_name> accounts (or whatever account has been designated as the anonymous web user) must be assigned this right.</machine_name></machine_name>	Administrators Users	Administrators
NOTE: If the network makes use of the Backup Operators or similar group, also assign this right to that group.		

User Rights	Windows 2000 Workstations	Windows 2000 Domain Controllers and Member Servers
Manage auditing and security log Allows a user to view and clear the security log and specify what types of object access (such as file access) are to be audited. Users with this right can enable auditing for a specific object by editing the auditing options in the security tab of the object's Properties dialog box. Members of the Administrators group always have the ability to view and clear the security log. NOTE: This right does not allow a user to enable file and object access auditing in	Administrators	Administrators
<ul> <li>general. Object auditing is enabled by setting the "Audit object access" item under Audit Policies.</li> <li>WARNING: If running Exchange 2000 on the network, the Exchange Enterprise Servers group must be assigned this user right on domain controllers.</li> </ul>		
Modify firmware environment variables Allows a user to modify system environment variables stored in nonvolatile RAM on systems that support this type of configuration.	Administrators	Administrators
Profile single process         Allows a user to perform profiling (performance sampling) on a process.         NOTE: Software developers working on the system may need this right. Assign the right to developer users/groups only when necessary.	Administrators	Administrators
Profile system performance Allows a user to perform profiling (performance sampling) on the system.	Administrators	Administrators
Remove computer from docking station Allows a user to undock a laptop from a docking station.	Administrators Users	(No one)
Replace a process-level token Allows a user to modify a process's security access token. This is a powerful right used only by the system.	(No one)	(No one)
Restore files and directories         Allows a user to restore backed-up files and directories. This right supercedes file and directory permissions.         NOTE: If the network makes use of the group to Restore backups, also assign this right to that group.	Administrators	Administrators

User Rights	Windows 2000	Windows 2000 Domain
	Workstations	Controllers and Member
		Servers
Shut down the system	Administrators	Administrators
Allows a user to shut down Windows 2000.	Users	Auministrators
Synchronize directory service data		
This right has no effect in the initial release of	(No one)	(No one)
Windows 2000.		
Take ownership of files or other objects		
Allows a user to take ownership of files,		
directories, printers, and other objects on the	Administrators	Administrators
computer. This right supersedes permissions		
protecting objects.		

#### **Table 7 User Rights Options**

#### Security Options

The Security Templates Security Option section contains many security parameters that can be easily configured by adding or changing registry key values. **Table 8** lists the recommended settings. Customized security options added to the NSA templates are shaded.

M	
25	
Ë)	
U	

WARNING: Use the Security Configuration Tool Set when configuring Security Options. Using the registry editor incorrectly can cause serious, system-wide problems that may require reinstallation of Windows 2000.

	Deserve	
Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
Additional restrictions for anonymous connections Places restrictions on anonymous users. The options are:	No access without explicit anonymous permissions	No access without explicit anonymous permissions
None. Rely on default permissions. Default permissions allow anonymous users to enumerate the names of domain accounts and network shares and have the same amount of access to resources as the "Everyone" group. The registry value for this option is 0.		
Do not allow enumeration of SAM accounts and		
shares. Replaces the "Everyone" group with "Authenticated Users" in resource security permissions. The registry value for this option is 1.		
<b>No access without explicit anonymous permissions.</b> Requires that "Anonymous" be given explicit permissions to access resources by removing the "Everyone" and "Network" groups from the anonymous user token. The registry value for this option is 2.		
WARNING: Setting the Restrict Anonymous key value = 2 could result in undesired effects when setting up trust relationships, authenticating in a mixed environment, or running certain services or applications. Please see KB Article Q246261 http://support.microsoft.com/support/ kb/articles/Q246/2/61.asp for further information on setting this key. If setting the key = 2 is not feasible, it is recommended that the value be set to "Do not allow enumeration of SAM accounts and shares" (value = 1).		
HKLM\System\CurrentControlSet\Control\Lsa\ RestrictAnonymous = 2		
Allow Automatic Administrator Logon Allows a system to automatically logon as administrator when the machine is started. By default, this setting is disabled. NOTE: If this option was at one time enabled, a DefaultPassword registry value may also exist in the same registry key. This value contains the administrator password in clear text and should be deleted.	Disabled	Disabled
HKLM\Software\Microsoft\Windows NT\CurrentVersion\ Winlogon\AutoAdminLogon = 0		

Security Attribute	Recommended Security Setting For Workstations and Member Servers	Recommended Security Setting For Domain Controllers
Allow Server Operators to schedule tasks (domain controllers only) Allows Server Operators to use the Schedule Service (AT command) to schedule a task to automatically run. By default, Administrators are able to schedule tasks. Options are:	Not defined	Disabled
Disabled Only allow Administrators to schedule tasks Enabled Allow Administrators and Server Operators to schedule tasks		
HKLM\System\CurrentControlSet\Control\Lsa\ SubmitControl= 0		
Allow system to be shut down without having to log on On Windows 2000 Professional, a Shutdown button is available in the Logon dialog box. When this option is disabled, users must be able to log on to the system and have the "Shut down the system" user right in order to shutdown the computer. By default, this option is disabled on servers. HKLM\Software\Microsoft\Windows\CurrentVersion\	Disabled	Disabled
Policies\System\ShutdownWithoutLogon = 0 Allowed to eject removable NTFS media By default, only Administrators are allowed to eject removable NTFS media. This setting allows for the following options: Administrators	Administrators	Administrators
Administrators and Power Users Administrators and Interactive Users		
HKLM\Software\Microsoft\Windows NT\ CurrentVersion\winlogon\AllocateDASD = 0 Amount of idle time required before disconnecting	30 minutes	30 minutes
session         Sets the amount of continuous idle time in a Server         Message Block (SMB) session before a session is         disconnected. If client activity resumes after a disconnect,         the session is automatically reestablished. Allowable         values are between 0 (Do not disconnect clients) and         99,999 minutes         HKLM\System\CurrentControlSet\Services\         LanManServer\Parameters\AutoDisconnect = 15		

Templates
Policy Settings with Security
Chapter 4 – Modifying Local

Security Attribute	Recommended Security Setting For Workstations	Recommended Security Setting For Domain
	and Member	Controllers
	Servers	
Audit the access of global system objects When enabled, this option will assign a default SACL to system objects such as mutexes, events, semaphores, and DOS devices. In order for these system objects to be audited, Audit Object Access must be enabled under auditing.	Enabled	Enabled
HKLM\System\CurrentControlSet\Control\Lsa\ AuditBaseObjects = 1		
Audit use of Backup and Restore privilege Enables auditing of all user rights in conjunction with Audit Privilege Use auditing being enabled. If this option is disabled, the Backup and Restore rights will not be audited even if Audit Privilege Use is enabled.	Enabled	Enabled
NOTE: Since there could be many Backup and Restore events generated during the course of system backups, this option may be disabled if there are concerns about the growth of the security log.		
HKLM\System\CurrentControlSet\Control\Lsa\ FullPrivilegeAuditing =1		
Automatically log off users when logon time expires Causes client SMB sessions to be forcibly disconnected when a user's logon hours expire. This setting affects all machines in a domain and should be set at the domain- level group policy.	Not Defined	Not defined
Automatically log off users when logon time expires	Enabled	Enabled
(local) Causes client SMB sessions to be forcibly disconnected when a user's logon hours expire. This policy affects the local machine on which it is applied.		
HKLM\System\CurrentControlSet\Services\ LanManServer\Parameters\EnableForcedLogoff = 1		
Clear virtual memory pagefile when system shuts down Wipes the system pagefile clean when Windows 2000 shuts down, ensuring that sensitive information that may be in the pagefile is not available to malicious users. When this option is enabled, it also causes the hibernation file (hiberfil.sys) to be cleared when hibernation is disabled on a laptop system.	Enabled	Enabled
HKLM\CurrentControlSet\Control\SessionManager\ MemoryManagement\ClearPageFileAtShutdown = 1		

	<b>D</b>	<b>D</b>
Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
		Controller 5
Disitally size alignt communication (always)	Servers Disabled	Disabled
Digitally sign client communication (always) Forces an SMB client to always digitally sign SMB	Disabled	Disabled
communications. Digital signatures provide mutual		
authentication during SMB exchanges, preventing "man-		
in-the-middle" and active message attacks.		
NOTE: To use SMB digital signing,		
this option must be enabled on both		
the SMB client and server.		
HKLM\System\CurrentControlSet\Services\		
RequireSecuritySignature = 0 Digitally sign client communication (when possible)	Enabled	Enabled
Enables an SMB client to perform digital packet signing		Enabled
when communicating with an SMB server that also		
supports packet signing. Digital signatures provide mutual		
authentication during SMB exchanges, preventing "man-		
in-the-middle" and active message attacks.		
HKLM\System\CurrentControlSet\Services\		
LanmanWorkstation\Parameters\		
EnableSecuritySignature = 1		
Digitally sign server communication (always)	Disabled	Disabled
Forces an SMB server to always digitally sign SMB communications. Digital signatures provide mutual		
authentication during SMB exchanges, preventing "man-		
in-the-middle" and active message attacks.		
NOTE: To use SMB digital signing, this option must be enabled on both		
the SMB client and server.		
HKLM\System\CurrentControlSet\Services		
LanmanServer\Parameters\RequireSecuritySignature = 0		
Digitally sign server communication (when possible)	Enabled	Enabled
Enables an SMB server to perform digital packet signing		
when communicating with an SMB client that also		
supports packet signing. Digital signatures provide mutual authentication during SMB exchanges, preventing "man-		
in-the-middle" and active message attacks.		
HKLM\System\CurrentControlSet\Services\		
LanmanServer\Parameters\EnableSecuritySignature = 1		

Templates
Policy Settings with Security
Chapter 4 – Modifying Local

Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	Controller 3
Disable CTRL+ALT+DEL requirement for logon	Disabled	Disabled
If this option is enabled, a user is not required to press	Disabiou	Diodolog
CTRL+ALT+DEL to log on. CTRL+ALT+DEL establishes		
a trusted path to the operating system when entering a username/password pair; therefore, disabling it poses a		
security risk to the users' logon credentials. By default,		
this option is disabled on systems in a domain and		
enabled on stand-alone workstations.		
HKLM\Software\Microsoft\Windows\CurrentVersion\		
Policies\System\DisableCAD = 0	All Drives	All Drives
Disable Media Autoplay Autoplay reads from a drive as soon as it is inserted. By	All Drives	All Drives
default, Windows 2000 autoruns any CDROM that is		
placed in the drive. This could allow executable content to		
be run without any access to the command prompt. Autoplay on floppy disks and network drives is disabled by		
default. The options for this setting are:		
CDROM drives		
Disables autorun on CDROMs. Registry value =		
0x00000095		
All drives		
Disables autorun on all media. Registry value =		
0x000000FF		
NOTE: This option can also be set in		
Group Policy via Computer		
Configuration\Administrative		
Because it is considered a security-		
related item, it has been added to the security templates here.		
NOTE: CDROM autoplay/autorun can		
also be disabled by setting the registry value		
HKLM\System\CurrentControlSet\Serv		
ices\Cdrom\Autorun = 0		
HKLM\Software\Microsoft\Windows\CurrentVersion\		
Policies\Explorer\NoDriveTypeAutoRun = 0x000000FF		

Socurit	ty Attribute	Recommended	Recommended
Securi	ly Attribute		
		Security Setting	Security
		For	Setting
		Workstations	For Domain
		and Member	Controllers
		Servers	
By defaul user to lo prevent n user nam logon. Th accessibl administr	isplay last user name in logon screen It, Windows 2000 displays the name of the last og on the computer in the <b>Logon</b> dialog box. To nalicious users from gaining information about thes on the system, disallow display of the last his is especially important if a generally the computer is being used for system ation.	Enabled	Enabled
Policies\S	System\DontDisplayLastUsername= 1		
This para authentic Windows authentic encrypted and crack secure. N available as well as	Tager authentication level Imeter specifies the type of challenge/response ation to be used for network logons with non- 2000 Windows clients. LanManager ation (LM) is the most insecure method, allowing d passwords to be easily sniffed off the network ked. NT LanManager (NTLM) is somewhat more ITLMv2 is a more robust version of NTLM and is with Windows NT 4.0 Service Pack 4 and higher s Windows 95/98 with Directory Services Client. wing options are available:	Send NTLMv2 response only\refuse LM & NTLM	Send NTLMv2 response only\refuse LM & NTLM
Send LM	<b>&amp; NTLM responses</b> - Registry value = 0.		
	I & NTLM – use NTLMv2 session security if ed - Registry value = 1.		
Send NT	<b>LM response only</b> - Registry value = 2.		
	<b>LMv2 response only</b> – System will still accept JTLM. Registry value = 3.		
Send NT value = 4	LMv2 response only∖refuse LM - Registry		
Registry	LMv2 response only\refuse LM and NTLM - value = 5.		
C	WARNING: Some Windows 2000 processes, such as Cluster Services, use NTLM to authenticate. Use of the recommended setting may cause these services to fail. For more information on NTLM and Cluster Services, see KB Article Q272129 <u>http://support.microsoft.com/sup</u> <u>port/kb/articles/Q272/1/29.ASP</u>		
	WARNING: Setting this value higher than 2 on a Windows 2000 system could prevent some connectivity to systems that support only LM authentication (Windows 95 <sup>®</sup> /98 <sup>®</sup> and		

Chapter 4 – Modifying Local Policy Settings with Security Templates

Security Attribute	Recommended Security Setting For Workstations and Member Servers	Recommended Security Setting For Domain Controllers
Windows for Workgroups <sup>®</sup> ) or only NTLM (Windows NT 4.0 prior to Service Pack 4). The Active Directory Services client may be installed on Windows 9x machines to allow for NTLMv2 security.		
WARNING: If adding a Windows 2000 machine to a Windows NT 4.0 domain, this value may need to be set to 4 "Send NTLMv2 response only\refuse LM" or lower on the Windows NT 4.0 domain controller.		
WARNING: Access to an Exchange server via IMAP and POP may not work from either Outlook 2000 or Outlook Express if this setting = 5. Instead, set this option to "Send NTLMv2 response only/refuse LM," value = 4. Service Pack 2 fixes this problem.		
HKLM\System\CurrentControlSet\Control\Lsa\ LMCompatibilityLevel = 5		

Security Attribute	Recommended Security Setting For	Recommended Security Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
Message text for users attempting to log on It is recommended that systems display a warning message before logon, indicating the private nature of the system. Many organizations use this message box to display a warning message that notifies potential users that their use can be monitored and they can be held legally liable if they attempt to use the computer without proper authorization. The absence of such a notice could be construed as an invitation, without restriction, to enter and browse the system. HKLM\Software\Microsoft\Windows\CurrentVersion\ Policies\System\LegalNoticeText = "Text you want displayed"	<configure -<br="" locally="">see Appendix for sample&gt;</configure>	<configure -<br="" locally="">see Appendix for sample&gt;</configure>
displayed" Message title for users attempting to log on	<configure -<="" locally="" td=""><td><configure -<="" locally="" td=""></configure></td></configure>	<configure -<="" locally="" td=""></configure>
In conjunction with the Logon Text, it is recommended that systems display a warning message title before logon, indicating the private nature of the system. HKLM\Software\Microsoft\Windows\CurrentVersion\ Policies\System\LegalNoticeCaption = "Text you want	see Appendix for sample>	see Appendix for sample>
displayed on title bar" Number of previous logons to cache (in case domain	0 logons	0 logons
controller is not available)The default Windows 2000 configuration caches the last10 logon credentials for users who log on interactively to asystem. This feature is provided for system availabilityreasons such as the user's machine being disconnectedfrom the network or domain controllers not beingavailable.WARNING: By setting this value to 0,users will NOT be able to log on to thedomain unless connected to thenetwork. This may have ramificationsfor mobile laptop users.WARNING: Not having cached logonsmay slow down the authenticationprocess.		
HKLM\Software\Microsoft\Windows NT\ CurrentVersion\Winlogon\CachedLogonsCount = 0		
Prevent system maintenance of computer account         password         By default, computer account passwords are changed         every seven days. Enabling this option prevents machines         from requesting a weekly password change.         HKLM\System\CurrentControlSet\Services\Netlogon\         Parameters\DisablePasswordChange = 0	Disabled	Disabled

# Chapter 4 – Modifying Local Policy Settings with Security Templates

Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
Prevent users from installing printer drivers	Enabled	Enabled
Prevents members of the users group from adding printer		
drivers on the local machine.		
NOTE: Users can still connect to		
Network Print shares to which they have permissions.		
WARNING: After enabling this option, users will not be able to add printers		
that have not been previously		
installed.		
HKLM\System\CurrentControlSet\Control\Print\Providers\		
LanMan Print Services\Servers\AddPrinterDrivers = 1		
Prompt user to change password before expiration	14 days	14 days
Sets how far in advance users are warned that their		
passwords will expire.		
HKLM\Software\Microsoft\Windows NT\CurrentVersion\		
Winlogon\PasswordExpiryWarning = 14		
Recovery Console: Allow automatic administrative	Disabled	Disabled
logon	Diodolog	Dicabled
If this option is enabled, the Recovery Console will not		
prompt for an administrator password and will		
automatically log on to the system.		
HKLM\Software\Microsoft\Windows NT\CurrentVersion\		
Setup\RecoveryConsole\SecurityLevel = 0		
Recovery Console: Allow floppy copy and access to	Disabled	Disabled
all drives and folders		
Enables the Recovery Console SET command, which		
allows setting of console environment variables such as		
AllowWildCards, AllowAllPaths, AllowRemovableMedia,		
and NoCopyPrompt.		
HKLM\Software\Microsoft\Windows NT\CurrentVersion\		
Setup\RecoveryConsole\SetCommand = 0		
Seruh/MeroveryConsole/SerContinuaria = 0		

Socurity Attribute		Decommended	Recommended
Security Attribute		Recommended	
		Security Setting	Security
		For	Setting
		Workstations	For Domain
		and Member	Controllers
		Servers	
Rename administrator account The Administrator account is of installing Windows 2000. Asso SID with a different name may who is targeting the built-in Ac choosing another name for thi names such as "admin" or "roo the account. After renaming th recommended that the default changed or deleted.	preated by default when bociating the Administrator of thwart a potential hacker liministrator account. When s account, avoid obvious ot," which reveal the use of he account, it is	<configure locally=""></configure>	<configure locally=""></configure>
NOTE: The provided define this setting d environment specifi However, renaming recommended settin	ue to the city of this option. this account is a		
NOTE: Even after re in domain administr will appear as Admin Directory Users and However, double-cli account, and clickin in the Properties wir that the logon name changed.	ator account, it nistrator in Active Computers. cking on the g the Account tab ndow will show		
WARNING: After con option via Group Po and 1202 may appea Application event lo minutes. See KB art http://support.micro kb/articles/Q260/7/11 information.	licy, event ID 1000 ar in the g every five icle Q260715 <u>soft.com/support/</u>		
Rename guest Account		<configure locally=""></configure>	<configure locally=""></configure>
The Guest account is created Windows 2000, but is disabled with a different name may thw targeting the built-in Guest acc account, it is recommended th description be changed or dele	d. Associating the Guest SID art a potential hacker who is count. After renaming the lat the default account		
NOTE: The provided define this settir environment specifi However, renaming recommended settir	ng due to the city of this option. this account is a		
NOTE: Even after re in domain guest appear as Guest ir Users and Comp double-clicking on	account, it will Active Directory puters. However,		

# Chapter 4 – Modifying Local Policy Settings with Security Templates

Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
clicking the Account tab in the		
Properties window will show that the logon name has indeed been changed.		
Restrict CD-ROM access to locally logged on user	Enabled	Enabled
onlyBy default, Windows 2000 allows any program to accessfiles on CD-ROM drives. In a highly secure, multi-userenvironment, it only allows interactive users to accessthese devices. When operating in this mode, the CD-ROM(s) are allocated to a user as part of the interactivelogon process. These devices are automaticallydeallocated when the user logs off.WARNING: There exists a known bugwhen installing Office 2000 from a CDand having this option enabled. Thiserror may appear as "Error 1311:Source fileexists and that you can access it." Asimilar error could occur with othersoftware CD installations (e.g.Windows 2000 Resource Kit).Currently, the only solutions are as		
follows: • Install the software from across the network		
Or		
Copy the contents of the CD to the hard drive, then install		
Or		
<ul> <li>Temporarily disable this setting, install the software, then re-enable it.</li> </ul>		
For more information, refer to KB Article Q230895 <u>http://support.microsoft.com/support/</u> kb/articles/Q230/8/95.asp.		
HKLM\Software\Microsoft\Windows NT\ CurrentVersion\Winlogon\ AllocateCDRoms = 1		
Restrict floppy access to locally logged on user only By default, Windows 2000 allows any program to access files on floppy drives. In a highly secure, multi-user environment, it only allows interactive users to access these devices. When operating in this mode, the floppy disks are allocated to a user as part of the interactive logon process. These devices are automatically deallocated when the user logs off.	Enabled	Enabled
HKLM\Software\Microsoft\Windows NT\		

Security Attribute	Recommended Security Setting For Workstations	Recommended Security Setting For Domain
	and Member	Controllers
	Servers	
CurrentVersion\Winlogon\ AllocateFloppies = 1 Secure channel: Digitally encrypt or sign secure	Disabled	Disabled
channel data (always)         Forces a computer to always digitally encrypt or sign secure channel data. A secure channel is created between a system and its domain controller when the system boots. By default, communications sent via the secure channel are authenticated and sensitive information, such as passwords, is encrypted, but the channel is not integrity checked and not all information is encrypted. This option will encrypt or sign all data passing through the secure channel.         NOTE: ALL domain controllers in ALL trusted domains must support digital		
<pre>encryption and signing if this option is enabled. HKLM\System\CurrentControlSet\Services\Netlogon\ Parameters\RequireSignorSeal = 0</pre>		
Secure channel: Digitally encrypt secure channel data (when possible) Enables a computer to digitally encrypt secure channel data. See the explanation of secure channel communication in the previous option.	Enabled	Enabled
If this option is enabled, all outgoing secure channel traffic should be encrypted.		
HKLM\System\CurrentControlSet\Services\Netlogon\ Parameters\SealSecureChannel = 1		
Secure channel: Digitally sign secure channel data (when possible) Enables a computer to digitally sign secure channel data. See the explanation of secure channel communication in the previous option.	Enabled	Enabled
If this option is enabled, all outgoing secure channel traffic should be signed.		
NOTE: If Digitally encrypt secure channel data (when possible) is enabled, it will override any setting for this option and automatically enable it.		
HKLM\System\CurrentControlSet\Services\Netlogon\ Parameters\SignSecureChannel = 1		

Security Attribute Recommended			
For     Setting       For     Workstations and Member Servers     For Domain Controllers       Secure channel: Require strong (Windows 2000 or itter) session key     Disabled     Disabled       Requires strong encryption keys for all outgoing secure channel communications.     Disabled     Disabled       Image: Servers     NOTE: This option should be enabled only if ALL domain controllers in ALL trusted domains also support strong session keys.     Disabled     Disabled       HKLMNSystem/CurrentControlSet/Services\Netlogon\ Parameters\RequireStrongKey = 0     Not defined     Not defined       Secure system partition (for RISC platforms only) Restricts access of the RISC system partition (which is FAT) to administrators only when the operating system is running.     Not defined     Not defined       Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication, or if there is a newer version of the product that adds this support.     Disabled     Disabled       WARNING: Enabling this will allow urenerrypted (plain text) passwords to be sert across the network when authentication of the consequences of plain text passwords in your specific environment.     Warning this server that requests this option. This reduces the coverall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.     HKLMSystem/CurrentControlSet/Services\ LammanWorkstation/Parameters\	Security Attribute	Recommended	Recommended
Workstations and Member Servers         For Domain Controllers           Secure channel: Require strong (Windows 2000 or later) session key         Disabled         Disabled           Requires strong encryption keys for all outgoing secure channel communications.         Disabled         Disabled           Image: Secure Addition on the problem of the consequences of plain text passwords in your specific environment.         WarkNiverentControlSet/Services/ Lamman/Workstation/Parameters/         HKLM/System/CurrentControlSet/Services/ Lamman/Workstation/Parameters/		5 0	5
and Member Servers         Controllers           Secure channel: Require strong (Windows 2000 or later) session key         Disabled         Disabled           Requires strong encryption keys for all outgoing secure channel communications.         Disabled         Disabled           Image: Secure channel: Requires strong encryption keys for all outgoing secure channel communications.         Disabled         Disabled           Image: Secure channel: Communications.         NOTE: This option should be enabled only if ALL domain controllers in ALL trusted domains also support strong session keys.         Disabled         Disabled           HKLMSystem/CurrentControlSet/Services/Netlogon/ Parameters/RequireStrong/Key = 0         Parameters/RequireStrong/Key = 0         Not defined           Secure system partition (for RISC platforms only) Restricts access of the RISC system partition (which is FAT) to administrators only when the operating system is running.         Not defined         Not defined           Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication. Check with the vendor of the SMB server product that adds this support.         Disabled         Disabled           Image: WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authentication of the consequences of plain text passwords in your specific environment.         HKLMSystem/CurrentControlSet/Services/ LammaNVorkstation/Parameters/         List of the consequences of plain text passwords in your specific environment.		For	Setting
Servers           Secure channel: Require strong (Windows 2000 or later) session key         Disabled         Disabled           Requires strong encryption keys for all outgoing secure channel communications.         Disabled         Disabled           MOTE: This option should be enabled only if ALL domain controllers in ALL trusted domains also support strong session keys.         Disabled         Not           HKLMNSystem/CurrentControlSet/Services/Netlogon/ Parameters/RequireStrongKey = 0         Not defined         Not defined           Secure system partition (for RISC platforms only) Restricts access of the RISC system partition (which is FAT) to administrators only when the operating system is running.         Not defined         Disabled           Send unencrypted password to connect to third-party SMB servers         Disabled         Disabled         Disabled           Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication, or if there is a newer version of the product that adds this support.         Disabled         Disabled           WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.         HKLMSystem/CurrentControlSet/Services/ Lamman/Workstation/Parameters/         Lamman/Workstation/Parameters/		Workstations	For Domain
Secure channel: Require strong (Windows 2000 or later) session key         Disabled           Requires strong encryption keys for all outgoing secure channel communications.         Disabled         Disabled           NOTE: This option should be enabled only if ALL domain controllers in ALL trusted domains also support strong session keys.         Not TE: This option should be enabled only if ALL domain controllers in ALL trusted domains also support strong session keys.         Not defined           HKLMNSystem/CurrentControlSet/Services/Netlogon/ Parameters/RequireStrongKey = 0         Not defined         Not defined           Secure system partition (for RISC platforms only) Restricts access of the RISC system partition (which is running.         Not defined         Disabled           Send unencrypted password to connect to third-party SMB servers         Disabled         Disabled         Disabled           Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication, or if there is a newer version of the product that adds this support.         Disabled         Disabled           WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.         HKLMSystem/CurrentControlSet/Services\ Lamman/Workstation/Parameters\		and Member	Controllers
Iater) session key         Requires strong encryption keys for all outgoing secure channel communications.         Image: Channel communication.         Some non-Microsoft SMB servers only support         Image: Channel communication.         Image: Channel co		Servers	
Requires strong encryption keys for all outgoing secure channel communications.       Image: Communication in the stress of the st		Disabled	Disabled
Image: Service of the service of th	Requires strong encryption keys for all outgoing se	ecure	
Parameters/RequireStrongKey = 0       Not defined         Secure system partition (for RISC platforms only)       Not defined         Restricts access of the RISC system partition (which is FAT) to administrators only when the operating system is running.       Not defined         Send unencrypted password to connect to third-party       Disabled       Disabled         SMB servers       Some non-Microsoft SMB servers only support       Disabled       Disabled         Some non-Microsoft SMB servers only support       unencrypted (plain text) password exchanges during       Disabled       Disabled         with the vendor of the SMB server product to see if there is a way to support encrypted       password authentication, or if there is a newer version of the product that adds this support.       WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.       HKLMNSystem\CurrentControlSet\Services\LanmanWorkstation\Parameters\	only if ALL domain controllers in ALL trusted domains also support strong		
Secure system partition (for RISC platforms only)       Not defined       Not defined         Restricts access of the RISC system partition (which is running.       Not defined       Not defined         Send unencrypted password to connect to third-party       Disabled       Disabled         SMB servers       Some non-Microsoft SMB servers only support       unencrypted (plain text) password exchanges during       Disabled       Disabled         Some non-Microsoft SMB servers only support       unencrypted (plain text) password exchanges during       Disabled       Disabled         with the vendor of the SMB server       product that adds this support.       Warning:       Warning:       Warning:         with the vendor of the SMB server       product that adds this support.       Warning:       Warning:       Warning this will allow         with the vendor of the some server       with the vendor of the some reversion of the product that adds this support.       Warning this will allow       Warning this will allow       Warning this of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.       HKLMNSystem\CurrentControlSet\Services\LanmanWorkstation\Parameters\       History and the consequences of plain text parameters\		/nc	
Restricts access of the RISC system partition (which is FAT) to administrators only when the operating system is running.       Disabled         Send unencrypted password to connect to third-party SMB servers       Disabled       Disabled         Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication. Check with the vendor of the SMB server product to see if there is a way to support encrypted password authentication, or if there is a newer version of the product that adds this support.       Disabled         WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.       HKLMNSystem\CurrentControlSet\Services\ LanmanWorkstation\Parameters\		ha Net define d	Not dofine al
FAT) to administrators only when the operating system is running.       Disabled         Send unencrypted password to connect to third-party SMB servers       Disabled         Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication. Check with the vendor of the SMB server product to see if there is a way to support encrypted password authentication, or if there is a newer version of the product that adds this support.       Disabled         WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.       HKLM\System\CurrentControlSet\Services\LanmanWorkstation\Parameters\			Not defined
Send unencrypted password to connect to third-party       Disabled       Disabled         SMB servers       Some non-Microsoft SMB servers only support       Disabled       Disabled         Some non-Microsoft SMB servers only support       Disabled       Disabled         unencrypted (plain text) password exchanges during       Disabled       Disabled         authentication. Check with the vendor of the SMB server       product to see if there is a way to support encrypted       password authentication, or if there is a newer version of         the product that adds this support.       WARNING: Enabling this will allow       unencrypted (plain text) passwords to         be sent across the network when       authenticating to an SMB server that       requests this option. This reduces the       overall security of an environment         and should only be done after careful       consideration of the consequences of       plain text passwords in your specific         environment.       HKLM\System\CurrentControlSet\Services\       LanmanWorkstation\Parameters\			
SMB servers         Some non-Microsoft SMB servers only support         unencrypted (plain text) password exchanges during         authentication. Check with the vendor of the SMB server         product to see if there is a way to support encrypted         password authentication, or if there is a newer version of         the product that adds this support.         WARNING: Enabling this will allow         unencrypted (plain text) passwords to         be sent across the network when         authenticating to an SMB server that         requests this option. This reduces the         overall security of an environment         and should only be done after careful         consideration of the consequences of         plain text passwords in your specific         environment.         HKLM\System\CurrentControlSet\Services\         LanmanWorkstation\Parameters\		d sestur Dischlad	Dischlad
Some non-Microsoft SMB servers only support unencrypted (plain text) password exchanges during authentication. Check with the vendor of the SMB server product to see if there is a way to support encrypted password authentication, or if there is a newer version of the product that adds this support.WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.HKLM\System\CurrentControlSet\Services\ LanmanWorkstation\Parameters\		Disabled	Disabled
authentication. Check with the vendor of the SMB server product to see if there is a way to support encrypted password authentication, or if there is a newer version of the product that adds this support.         Image: Warning: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.         HKLM\System\CurrentControlSet\Services\LanmanWorkstation\Parameters\			
product to see if there is a way to support encrypted         password authentication, or if there is a newer version of         the product that adds this support.         WARNING: Enabling this will allow         unencrypted (plain text) passwords to         be sent across the network when         authenticating to an SMB server that         requests this option. This reduces the         overall security of an environment         and should only be done after careful         consideration of the consequences of         plain text passwords in your specific         environment.         HKLM\System\CurrentControlSet\Services\         LanmanWorkstation\Parameters\			
<ul> <li>password authentication, or if there is a newer version of the product that adds this support.</li> <li>WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.</li> <li>HKLM\System\CurrentControlSet\Services\LanmanWorkstation\Parameters\</li> </ul>			
the product that adds this support.         WARNING: Enabling this will allow unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment.         HKLM\System\CurrentControlSet\Services\LanmanWorkstation\Parameters\			
unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific environment. HKLM\System\CurrentControlSet\Services\ LanmanWorkstation\Parameters\			
LanmanWorkstation\Parameters\	unencrypted (plain text) passwords to be sent across the network when authenticating to an SMB server that requests this option. This reduces the overall security of an environment and should only be done after careful consideration of the consequences of plain text passwords in your specific		

		Decemenated
Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
Shut down system immediately if unable to log	Enabled	Enabled
security audits		
If events cannot be written to the security log, the system is halted immediately. If the system halts as a result of a		
full log, an administrator must log onto the system and		
clear the log.		
NOTE: Before clearing the security		
log, save the data to disk.		
WARNING: Enabling this option will		
disallow any connections to the system until the audit logs are		
cleared. Take caution when enabling		
this on critical systems. Also, enabling this option on a large		
number of workstations in the		
network may result in much overhead when the logs become full.		
HKLM\System\CurrentControlSet\Control\Lsa\ CrashOnAuditFail = 1		
Smart card removal behavior	Lock Workstation	Lock Workstation
Determines the action taken when a smart card for a logged-on user is removed from the smart card reader.		
Options are:		
No action		
Lock Workstation		
Users can remove their smart card, leave the area, then		
return to their same session at a later time.		
Force Logoff		
Users are automatically logged off when the card is		
removed.		
HKLM\Software\Microsoft\Windows		
NT\CurrentVersion\Winlogon\ScRemoveOption = 1		
Strengthen default permissions of global system objects (e.g., Symbolic Links)	Enabled	Enabled
Strengthens the DACLs on the global list of shared		
system resources (such as DOS device names, mutexes,		
and semaphores) so that non-administrative users can		
read, but not modify shared objects they did not create.		
HKLM\Software\CurrentControlSet\Session Manager\		
ProtectionMode = 1		

# Chapter 4 – Modifying Loca Policy Settings with Securit Templates

## UNCLASSIFIED

Security Attribute	Recommended	Recommended
	Security Setting	Security
	For	Setting
	Workstations	For Domain
	and Member	Controllers
	Servers	
Unsigned driver installation behavior Determines the action taken when a device driver that has not been certified for Windows 2000 attempts to load. Options are:	Warn but allow installation	Warn but allow installation
Silently succeed		
Warn but allow installation		
Do not allow installation		
HKLM\Software\Microsoft\Driver Signing\Policy = 1		
Unsigned non-driver installation behavior Determines the action taken when non-device driver software that has not been certified for Windows 2000 attempts to load. Options are:	Warn but allow installation	Warn but allow installation
Silently succeed		
Warn but allow installation		
Do not allow installation		
HKLM\Software\Microsoft\Non-driver Signing\Policy = 1		

#### **Table 8 Security Options**

Several settings should be configured at the domain-level group policy object. These are configured in the "W2K Domain Policy.inf" template and are shown in **Table 9**.

Security Attribute	Recommended Setting
Automatically log off users when logon time expires	Enabled
Rename Administrator account	<configure locally=""></configure>
Rename Guest Account	<configure locally=""></configure>

#### **Table 9 Domain-wide Security Options**

#### Adding an Entry to Security Options

In the Windows 2000 Security Configuration Tool Set, it is possible to add additional registry key settings to the Security Options portion of a template. To accomplish this, perform the following actions:

- Open the file %SystemRoot%\inf\sceregvl.inf (%SystemRoot% is usually C:\winnt) in Notepad, Wordpad, or another text editor
- □ Add a line in the form regpath, type, displayname, displaytype where
  - *regpath* registry key value path, e.g., MACHINE\System\CurrentControlSet\Control\Lsa\AuditBaseObjects

- type data type of the registry entry represented by a number. Possible values are REG\_SZ (1), REG\_EXPAND\_SZ (2), REG\_BINARY (3), REG\_DWORD (4), REG\_MULTISZ (7)
- displayname the name actually displayed in the security template, e.g., "Audit the access of global system objects"
- displaytype How the interface will display the registry value type. Possible values are Boolean (0), number (1), string (2), choices (3). If choices are specified, the choices should then be specified in the format value1/display1,value2/display2,...
- Re-register scecil.dll by executing regsvr32 scecil.dll at a command prompt

An example line in sceregvl.inf is:

MACHINE\Software\Microsoft\WindowsNT\CurrentVersion\Winlogon\ScRemoveOption,1, %ScRemove%,3,0|%ScRemove0%,1|%ScRemove1%,2|%ScRemove2%

The strings listed above are defined in the [Strings] section of sceregvl.inf:

%ScRemove% = Smart card removal behavior

%ScRemove0% = No Action

%ScRemove1% = Lock Workstation

%ScRemove2% = Force Logoff

#### Deleting customized options

The deletion of customized security options is not as simple as removing the options from the sceregvl.inf file and re-registering the DLL. To ensure that options are permanently deleted from the templates, perform the following actions:

- Open sceregvl.inf in a text editor (e.g. Notepad)
- □ Delete the specific security option from the sceregvl.inf file under the [Register Registry Values] section
- □ Under the sceregvl.inf section labeled "delete these values from current system," add the registry key to be removed from the templates. For example, taking the example used in the previous section, place MACHINE\Software\Microsoft\WindowsNT\CurrentVersion\Winlogo n\ScRemoveOption under this section.
- □ Save and close sceregvl.inf
- □ At a command prompt, execute regsvr32 scecli.dll
- □ To confirm that the option has been deleted, open the Security Templates snapin in the MMC and verify that the option no longer appears in the Local Policies → Security Options section of the template files
- □ To clean up, edit sceregvl.inf again, remove the entry added previously under "delete these values from current system," save and close the file, then run regsvr32 scecli.dll again.

This Page Intentionally Left Blank



## Modifying Event Log Settings with Security Templates

Windows 2000 event logs record system events as they occur. The Security, Application, and System event logs contain information generated by the specified audit settings. In addition to the audit settings enabled in the security templates, auditing of other system objects, such as specific files, registry keys, and printers, can be enabled.

To view event log settings of a security template double-click the following:

- Security Templates
- Default configuration file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- Event Log



NOTE: After making any modifications to the configuration files, make sure the changes are saved and then test the changes before installing them on an operational network.

#### Event Log Settings

Event log settings that can be configured with the security templates include maximum size, guest access, how long logs will be retained, and how the operating system handles logs at the maximum size.

To modify Event Log Settings via the Security Templates, double-click the following path:

Event Log  $\rightarrow$  Settings for Event Logs  $\rightarrow$  specific option to view or edit

**Table 10** lists recommended Event Log settings for the Application, Security, and System logs.

Event Log Settings	Recommended
	Settings
Maximum application log size Maximum security log size Maximum system log size If the event logs are too small, logs will fill up often and administrators must save and clear the event logs more frequently than required. Allowable values range from 64 KB to 4194240 KB. NOTE: This setting will allow the log file to equal the size of the available space on the hard disk or up to 4GB, whichever is smaller. This ensures that the system will still halt if the event log exceeds 4 GB, even if there is space on the hard drive.	4194240 KBytes
Restrict guest access to application Log Restrict guest access to security LogRestrict guest access to system LogDefault configuration allows guests and null logons the ability to view event logs (system and application logs). While the security log is protected from guest access by default, it is viewable by users who have the Manage Audit Logs user right. This option disallows guests and null logons from viewing any of the event logs.	Enabled
Retain application logRetain security logRetain system logThese options control how long the event logs will be retained beforethey are overwritten. Allowable values are between 1 and 365 days.Since it is not recommended that any event logs be overwritten whenthey become full, this option should not be configured.	Not defined
Retention method for application LogRetention method for security LogRetention method for system LogHow the operating system handles event logs that have reached theirmaximum size. The event logs can be overwritten after a certainnumber of days, overwritten when they become full, or have to becleared manually. To ensure that no important data is lost, especially inthe event of a security breach of the system, the event logs should notbe overwritten.	Manually
Shut down the computer when the security audit log is full         If events cannot be written to the security log, the system should be halted immediately. If the system halts as a result of a full log, an administrator must restart the system and clear the log.         WARNING: Enabling this option will disallow any connections to the system until the audit logs are cleared. Take caution when enabling this on critical systems. Also, enabling this option on a large number of workstations in the network may result in much overhead when the logs become full.	Enabled

#### **Table 10 Event Log Options**

#### Managing the Event Logs

Security Options (discussed in Chapter 4) recommends enabling Audit the access of global system objects and Audit use of all user rights including Backup and

**UNCLASSIFIED** 

**Restore**. If these options are enabled, large amounts of audit data will be generated, requiring the logs to be cleared regularly.

#### Saving And Clearing the Audit Logs

To save and clear the logs:

- $\Box \quad \text{Select Start} \rightarrow \text{Programs} \rightarrow \text{Administrative Tools} \rightarrow \text{Event Viewer}$
- Click on the log to be cleared in the right pane of the Event Viewer window
- □ Select Clear All Events from the Action menu
- Click Yes to save settings with unique file name
- Specify where the log will be saved and then click Save
- Click Yes to clear the log
- Repeat the above steps for each log

#### Resetting the Audit Log Settings After the System Halts

If the system halts as a result of a full log, an administrator must restart the system and clear the log.

NOTE: Before clearing the security log, save the data to disk.

After saving the log, use the registry editor (regedt32.exe) to modify the following registry key value:

Hive:	HKEY_LOCAL_MACHINE
Key:	\System\CurrentControlSet\Control\Lsa
Name:	CrashOnAuditFail
Type:	REG_DWORD
Value:	1
	NOTE: This value is set by the operating system just before it crashes due to a full audit log. While the value is 2, only the administrator can log on to the computer. This value confirms the cause of the crash. Reset the value 1

This Page Intentionally Left Blank

Chapter

6

# Managing Restricted Groups with Security Templates

The Restricted Groups option allows the administrator to manage the membership of sensitive groups. For example, if the Administrators group is to only consist of the built-in Administrator account, the Administrators group can be added to the Restricted Groups option and Administrator can be added in the **Members of Administrators** column. This setting could prevent other users from elevating their privilege to the Administrators group through various attack tools and hacks.

Not all groups need to be added to the Restricted Group list. It is recommended that only sensitive groups be configured through security templates. Any groups not listed will retain their membership lists.


For all groups listed for this option, any groups and/or users listed which are not currently members of that group are added, and any users and/or groups currently members of the group but not listed in the configuration file are removed.

#### Modifying Restricted Groups via the Security Templates Snap-in

Since the settings in the Restricted Groups option should be environment-specific, only one restricted group setting is configured in the companion configuration (inf) files. However, a site may need to restrict the membership of additional sensitive groups within the domain.

To view restricted group settings of an SCM template double-click the following:

- □ Security Templates
- □ Default configuration file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- **D** Restricted Groups



The following steps describe how to add a restricted group to the list:

- □ Right-click Restricted Groups
- □ Select Add Group
- □ Click the Browse button

- $\hfill\square$  Double-click each group that needs to be added and  $OK \rightarrow OK$
- Double-click newly added group in the right frame
- □ Click Add
- Double-click each group and/or user who wish to be members of the group
- $\Box \quad \text{Click } OK \to OK$

The recommended setting in the provided workstation and member server templates restricts the Power Users group to having no members.

Chapter

7

## Managing System Services with Security Templates

The System Services option allows for configuration of startup modes and access control lists for all system services. Configuration options include startup settings (Automatic, Manual, or Disabled) for services such as network, file, and print services. Security settings can also be established that control which users and/or groups can read and execute, write to, delete, start, pause, or stop a service.

#### Modifying System Services via the Security Templates Snap-in

Because of the broad nature of this area, system service configuration is environmentspecific. Services not listed in this option can be added. However, a new DLL attachment will need to be created and attached. For more information on creating service attachments, refer to the white paper *Security Configuration Toolset* <u>http://www.microsoft.com/windows2000/library/howitworks/security/sctoolset.asp</u>.

To view system services settings of a security template double-click the following in the MMC:

- **Gamma** Security Templates
- □ Default configuration file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- □ System Services



NOTE: After making any modifications to the configuration files make sure the changes are saved, and then test the changes before installing them on an operational network.

The following steps describe how to configure system service settings;

- Double-click the service to configure
- Check the Define this policy setting in the template checkbox
- □ If this is policy was previously undefined, the Security dialog box will automatically appear. Otherwise, click Edit Security
- Click Add (to add groups and/or users to the access list)
- Double-click each user or group to add and **OK**
- Check the permissions that each user or group should have for that service
- □ Click Remove (to remove groups and/or users from the access list)

- D When finished entering the permissions, click OK
- □ Under Select service startup mode, select Automatic, Manual, or Disabled

Figure 4 shows the System Services entries in the Security Templates snap-in.

j ⊆onesle ⊎jindov tjelp			D 🚅 🖬 🔟	
lyction Yev Eavorites 🛛 💠 🕂 🚺 📆	13 B			
R Favorites	Service Name /	Startup	Perwepsion	
Console Roat	- Aierter	Not defined	Not defined	
Security Templates	SApplication Management	Not defined	Not defined	
E C/WIWIGeounty/Templates	Sipfook.	Not defined	Not defined	
🕸 🚺 basicdc	SCOM+ Event System	Not defined	Not defined	
😣 🚺 basicav	Computer Browser	Not defined	Not defined	
🔅 🚺 basicvé.	SchOP Client	Not defined	Not defined	
🛞 🎑 compañve	Citatributed Pile System	Not defined	Not defined	
DC security	Cistributed Link Tracking Client	Not defined	Not defined	
🛞 🛄 hirecdc	Cristributed Link. Tracking Server	Not defined	Not defined	
B Discours	Cistributed Transaction Coordinator	Not defined	Not defined	
🕀 🎑 natasid	SONS Clere	Not defined	Not defined	
Continue Con	CNS Server	Not defined	Not defined	
	Street Log	Not defined	Not defined	
<ul> <li>Becured:</li> <li>Becured:</li> </ul>	Tax Service	Not defined	Not defined	
E setup security	SPIE Replication Service	Not defined	Not defined	
B- Vizk DC	Sindexing Service	Not defined	Not defined	
E- Account Policies	Sinternet Connection Sharing	Not defined	Not defined	
E Al Local Policies	Submate Measaging	Not defined	Not defined	
E- A Event Log	PSEC Policy Agent	Not defined	Not defined	
E Redricted Groups	Kerberos Key Distribution Center	Not defined	Not defined	
System Serviced	Sticknoe Logging Service	Not defined	Not defined	
E Begittry	Crystol Disk Manager	Not defined	Not defined	
🕀 🎲 File System	Augical Disk Manager Administrative Service	Not defined	Not defined	
W2K Domain Policy Template	Ressenger	Not defined	Not defined	
🕀 🔂 W2K Server	Warriet Logan	Not defined	Not defined	
B W2K Workstation	AretMeeting Renote Desktop Sharing	Not defined	Not defined	
_	Avietwork Connections	Not defined	Not defined	
	Stetwork COE	Not defined	Not defined	
	Aletwork DDE DSDM	Not defined	Not defined	
	ANT UN Security Support Provider	Not defined	Not defined	
	Performance Logs and Alerts	Not defined	Not defined	
	Plug and Ray	Not defined	Not defined	
	Spring and Hay	Not defined	Not defined	
	Protected Starage	Not defined	Not defined	
	Cost R5VP		1000 000 0000	
	Security documents of the Connection Manager	Not defined Not defined	Not defined Not defined	

#### **Figure 4 System Services**

#### System Services Security

If compromised, services may offer direct access to system resources or fall victim to buffer overflows or denial of service attacks. Therefore, the proper configuration of services is an important security step. Since services are environment and application specific, no services are configured in this document. However, there are a few guidelines to consider when configuring services:

- Only run necessary services. For example, if the telnet service or FTP service is running on a system, but not being used, disable them.
- □ Ensure that only a limited number of users/groups can start, stop, or change a service.
- □ If a service is listed, but not needed, change the startup mode to Disabled instead of Manual. This will ensure that the service cannot be restarted by an unauthorized or malicious user.

When configuring either the startup mode or access control list for a service, you must configure the other as well. When a service is explicitly disabled, its ACL should also be secured by changing the default ACL from Everyone Full Control to grant Administrators and SYSTEM Full Control and Authenticated Users Read access.

This Page Intentionally Left Blank



## Modifying Registry Security Settings with Security Templates

The Security Configuration Tool Set can be used to configure discretionary access control lists (DACLs) for registry keys. In order to implement adequate security in a Windows 2000 environment, some registry key permissions should be changed. The recommended changes can also be made manually using regedt32.exe; however, this method is more time-consuming and leaves more room for error.



WARNING: By default, some protections are set on the various components of the registry that allow work to be done while providing standard-level security. For high-level security, additional access rights must be added to specific registry keys. This should be done with caution because programs that users need to do their jobs often require access to certain keys on the users' behalf. Care should be taken to follow these steps exactly, as additional, unnecessary changes to the registry can render a system unusable and even unrecoverable.

#### Inheritance model

Those who used the Security Configuration Manager with Windows NT 4.0 Service Pack 4 or higher may remember a new inheritance model with respect to registry and file discretionary access control lists (DACLs), i.e., permissions. Windows 2000 and NTFS version 5 implement the full functionality of this inheritance model. Within the new inheritance model, permissions on child objects are automatically inherited from their parent. This can be seen by the check in the **Allow inheritable permissions from parent to propagate to this object** checkbox in the DACL editor. More permissions can be explicitly defined for a child object in addition to those the child inherits from its parent.

When the checkbox is not checked, the DACLs defined on that object apply only to that object and its children. No permissions are inherited from the parent object.

#### **Registry permissions**

To manually view permissions on a specific registry key:

- □ Run regedt32.exe
- □ Select the desired registry key
- □ In the Registry Editor, select the Security menu
- □ Select Permissions...

Only Read and Full Control permissions appear in the permissions dialog box. However, permissions may be set with more granularity by clicking the **Advanced** button. **Table 11** shows a list of granular registry permissions. **Table 12** shows which granular permissions to select in order to achieve certain higher-level permissions.



**NOTE:** Any time a permission is not a pure Read or Full Control, the permission is noted as Special in the Advanced Access Control Settings window.

Special Permissions	Description
Query Value	Allows querying the registry for a specific value
Set Value	Allows new values to be created for a key and old values to be overwritten
Create Subkey	Allows the creation of subkeys
Enumerate Subkeys	Allows viewing of a list of subkeys under a registry key
Notify	Allows registration of a callback function that is triggered when the value changes
Create Link	Allows the creation of link to a specific key
Delete	Allows deletion of a value or key
Write DAC	Allows modification of access controls on the key
Write Owner	Allows a user to take ownership of a key
Read Control	Allows reading of the key's access control list

#### **Table 11 Registry Permissions and Descriptions**

Special Permissions	Full Control	Read	Write	Delete
Query Value	x	x		
Set Value	x		x	
Create Subkey	x		x	
Enumerate Subkeys	x	x		
Notify	x	x		
Create Link	x			
Delete	x			x
Write DAC	x			
Write Owner	x			
Read Control	х	х	x	

**Table 12 Registry Permission Options** 

#### Modifying Registry settings via the Security Templates snap-in

Within a security template, registry permissions may be customized by either modifying existing registry keys in an inf file, or by adding your own registry keys and permissions.

To view registry settings of a security template select the following:

- □ Security Templates
- Default file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- □ Registry

Modifying Permissions on a Registry Key

To modify the security settings on a particular registry key already specified in the inf file:

- □ In the right frame, double-click on the key to be changed
- □ Ensure that the **Configure this key then** radio button is selected. Under this option, there are two other options:
  - Propagate inheritable permissions to all subkeys all subkeys that already inherit permissions from the key being configured will inherit the new permissions. This option will have no effect on subkeys that do not have Allow inheritable permissions from parent to propagate to this object enabled in their DACLs.
  - Replace existing permissions on all subkeys with inheritable permissions all subkeys will have their permissions set to the new permissions and will inherit from the key being configured regardless of any inheritance or blocking of inheritance on subkeys.
- □ Click Edit Security
- □ Ensure that the Allow inheritable permissions from parent to propagate to this object checkbox is unchecked
- □ Modify users and groups to reflect the recommended permissions by clicking the Add or Remove buttons
- □ For each user and/or group, set the permissions by clicking on the permission checkboxes.
- □ The only permissions that appear in the **Permissions** dialog box are Read and Full Control. If these permissions are all that is desired, and if the key permissions should encompass the key itself and all subkeys below the key, click **Apply**  $\rightarrow$  **OK**. Stop here.

If extra granularity needs to be added to the permissions:

Click the Advanced button. Figure 5 shows the Advanced dialog box



NOTE: More granular permissions (special access) for a user and/or group can be configured through the Advanced dialog box.

cess Contro	ol Settings for machine\	software		?	
emissions	Auditing Owner				
Permission B	Entries:				
Туре	Name	Pemission	Apply to		
Allow	Administrators (88 VAdmi	Full Control	This key and subkeys		
Allow	CREATOR OWNER	Full Control	Subkeys only		
Allow	SYSTEM	Full Control	This key and subkeys		
Allow	Users (8B\Users)	Read	This key and subkeys		
Add.	. <u>R</u> emove	<u>View/Edit</u>			
This permiss	This permission is defined directly on this object. This permission is inherited by child objects.				
Allow inh	eritable permissions from para	ani lo monanale	to this object		
- ADM FD	criticale permissions nom par	our co propogaco	to the support		
		OK	Cancel /	apply .	
		OK.	Cancel	3pply	

Figure 5 Advanced Registry Permissions Dialog Box

- □ Click on a user and/or group
- Click View/Edit. A Permission Entry dialog box will appear
- □ In the Apply onto pull-down menu, select the correct configuration. Possible values are: This key only, This key and subkeys, and Subkeys only
- □ In the Permissions pane, select the desired permissions. Refer to the earlier section on registry permissions
- $\Box \quad \text{Click } OK \to OK \to OK \to OK \text{ to exit}$

Adding registry keys to the security configuration

To add a registry key to the security configuration:

- □ Right-click on Registry
- Select Add Key from the pull-down menu
- □ Select the registry key to be added
- Click OK
- □ A Configuration Security dialog box will appear
- □ Click OK
- Double-click on the registry key in the right frame when it appears
- □ Configure the permissions according to the steps detailed in the previous **Modifying permissions on a registry key** section.

#### Excluding registry keys from the security configuration

There are occasions where a specific registry key should retain its current security settings. To ensure that parent keys do not propagate their new permissions down to such registry keys, the object may be excluded from configuration.

To exclude an object:

- □ In the right frame of Registry, double-click on the key to be changed
- Click the Do not allow permissions on this key to be replaced radio button.
- Click OK

#### Recommended Registry Key Permissions

Registry keys not explicitly listed below in **Table 13** are assumed to inherit the permissions of their parent key if they already have **Allow inheritable permissions from parent to propagate to this object** checked in their DACL. Keys with "Ignore" selected are explicitly excluded from security configuration and retain their original permissions.

In the table, the term "Propagate" indicates that the **Propagate inheritable permissions to** all subkeys radio button should be enabled while "Replace" indicates that the **Replace** existing permissions on all subkeys with inheritable permissions radio button should be enabled.



NOTE: Several of the security settings listed below are based on Microsoft's high security template (hisecws.inf). Microsoft chose to exclude several keys by setting the "Ignore" attribute in order to maintain the default security settings. It cannot be assumed that these default settings have not been modified in the past. Therefore, it was decided to explicitly set permissions on some of these keys to reflect what the default permissions should be. In such cases, the "Propagate" option was selected.

The following notation is used in this section of the security templates:

- CLASSES\_ROOT indicates HKEY\_CLASSES\_ROOT hive
- MACHINE indicates HKEY\_LOCAL\_MACHINE hive
- USERS indicates HKEY\_USERS hive

In the domain controller security template, "W2K DC.inf," all instances of the **Users** group have been replaced with the **Authenticated Users** group.

REGISTRY KEY	USER GROUPS	RECOMMENDED	INHERIT
		PERMISSIONS	METHOD
CLASSES_ROOT\	Administrators	Full Control	Replace
Alias to MACHINE\SOFTWARE\Classes.	CREATOR OWNER	Full Control	
Contains file associations and COM (Common	SYSTEM	(Subkeys only) Full Control	
Object Model) associations.	Users	Read	
MACHINE\SOFTWARE	Administrators	Full Control	Replace
	CREATOR OWNER	Full Control	Replace
		(Subkeys only)	
Contains information about the software	SYSTEM	Full Control	
installed on the local system.	Users	Read	
\MACHINE\SOFTWARE\Microsoft\NetDDE	Administrators	Full Control	Replace
	SYSTEM	Full Control	
Settings for Network Dynamic Data Exchange,			
which is a protocol that allows applications to			
exchange data.			
\MACHINE\SOFTWARE\Microsoft\	Administrators	Full Control	Replace
OS/2 Subsystem for NT	CREATOR OWNER	Full Control	
Contains support for OC/2 standards. Even if	OVOTEM	(Subkeys only) Full Control	
Contains support for OS/2 standards. Even if this key is removed, it will reappear at next boot	SYSTEM	Full Control	
up.			
MACHINE\SOFTWARE\Microsoft\	Ignore		Ignore
Protected Storage System Provider	ignore		Ignore
rotototo ofototago ofototin riovidor			
Used to protect user data. Inaccessible.			
\MACHINE\SOFTWARE\Microsoft\	Administrators	Full Control	Replace
Windows NT\CurrentVersion\AsrCommands	Backup Operators	Query, Set Value,	
		Create Subkey,	
Automatic Server Recovery commands.		Enumerate, Notify,	
		Delete, Read	
NOTE: If not using the Backup Operators group,		permissions	
remove the group from	CREATOR OWNER	Full Control	
these permissions.	SYSTEM	(Subkeys only) Full Control	
	Users	Read	
\MACHINE\SOFTWARE\Microsoft\	Administrators	Full Control	Replace
Windows NT/CurrentVersion/Perflib	INTERACTIVE	Read	Replace
	CREATOR OWNER	Full Control	
Parameters for the Performance Library, which	SYSTEM	Full Control	
collects information for Performance Monitor.			
Contains a language code subkey for each			
spoken language configured on the			
Windows 2000 system. For example, a subkey			
named 009 contains counters and descriptions			
for the language code English (United States).			
MACHINE\SOFTWARE\Microsoft	Administrators	Full Control	Propagate
Windows\CurrentVersion\Group Policy	Authenticated Users	Read	
Contains data for Group Policy settings that	STOTEIVI	Full Control	
configure the Group Policy components of			
Windows 2000. Contains subkeys representing			
each of the client-side extensions used to			
create settings in Group Policy.			
\MACHINE\SOFTWARE\Microsoft\Windows\	Administrators	Full Control	Propagate
CurrentVersion\Installer	SYSTEM	Full Control	
	Users	Read	
Contains configuration information for the			
Windows Installer.	1	1	1

		RECOMMENDED	INHERIT
REGISTRY KEY	USER GROUPS	PERMISSIONS	METHOD
\MACHINE\SOFTWARE\Microsoft\Windows \ CurrentVersion\Policies	Administrators Authenticated Users	Full Control Read	Propagate
Stores registry entries managed by Group Policy. Manages entries for the following subkeys:	SYSTEM	Full Control	
HKLM\SOFTWARE\Policies			
HKLM\SOFTWARE\Microsoft\Windows\ CurrentVersion\Policies			
HKCU\SOFTWARE\Policies			
HKCU\SOFTWARE\Microsoft\Windows\ CurrentVersion\Policies			
<u>\MACHINE\SYSTEM</u>	Administrators CREATOR OWNER	Full Control Full Control	Replace
Stores values for the current control set or control sets that have been previously used to start Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	
\MACHINE\SYSTEM\clone	Ignore		Ignore
\MACHINE\SYSTEM\controlset001	Administrators CREATOR OWNER	Full Control Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset002	Administrators	Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	CREATOR OWNER SYSTEM Users	Full Control (Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset003	Administrators	Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	CREATOR OWNER SYSTEM Users	Full Control (Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset004	Administrators CREATOR OWNER	Full Control Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset005	Administrators CREATOR OWNER	Full Control Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset006	Administrators CREATOR OWNER	Full Control Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	
\MACHINE\SYSTEM\controlset007	Administrators CREATOR OWNER	Full Control	Propagate
Contains a control set that may be used to start and run Windows 2000.	SYSTEM Users	(Subkeys only) Full Control Read	

REGISTRY KEY	USER GROUPS	RECOMMENDED	INHERIT
	Administrators	PERMISSIONS Full Control	METHOD
MACHINE\SYSTEM\controlset008	CREATOR OWNER	Full Control	Propagate
Contains a control set that may be used to start	one/non ownen	(Subkeys only)	
and run Windows 2000.	SYSTEM	Full Control	
	Users	Read	
MACHINE\SYSTEM\controlset009	Administrators	Full Control	Propagate
Contains a control act that may be used to start	CREATOR OWNER	Full Control	
Contains a control set that may be used to start and run Windows 2000.	SYSTEM	(Subkeys only) Full Control	
	Users	Read	
MACHINE\SYSTEM\controlset010	Administrators	Full Control	Propagate
	CREATOR OWNER	Full Control	-1-5
Contains a control set that may be used to start		(Subkeys only)	
and run Windows 2000.	SYSTEM	Full Control	
	Users	Read	
MACHINE\SYSTEM\CurrentControlSet\	Administrators	Full Control	Replace
Control\SecurePipeServers\winreg	Backup Operators SYSTEM	Read (Key only) Full Control	
The security permissions set on this key define	STOTEW		
which users or groups can connect to the			
system for remote registry access. If the key			
does not exist, anyone can remotely connect to			
he registry. It is highly recommended that only			
administrators have remote access to the			
registry.			
NOTE: If not using the Backup Operators group, remove the group from these permissions.			
WARNING: Microsoft Exchange 2000 requires remote registry access. Therefore, on Exchange servers and domain controllers within the domain, add the Exchange Domain Servers group with Full Control access on this registry key.			
MACHINE\SYSTEM\CurrentControlSet\	A duration in the state way	Full Control	Replace
	Administrators		
	CREATOR OWNER	Full Control	
Control/Wmi/Security			
Control/Wmi/Security Security settings for the Windows Management Instrumentation (WMI). WMI is the Microsoft	CREATOR OWNER	Full Control	
Control/Wmi/Security Security settings for the Windows Management nstrumentation (WMI). WMI is the Microsoft mplementation of Web-Based Enterprise	CREATOR OWNER	Full Control	
Control/Wmi/Security Security settings for the Windows Management nstrumentation (WMI). WMI is the Microsoft mplementation of Web-Based Enterprise Management (WBEM).	CREATOR OWNER SYSTEM	Full Control	
Control/Wmi/Security Security settings for the Windows Management Instrumentation (WMI). WMI is the Microsoft mplementation of Web-Based Enterprise Management (WBEM).	CREATOR OWNER SYSTEM	Full Control	Ignore
Control/Wmi/Security Security settings for the Windows Management Instrumentation (WMI). WMI is the Microsoft implementation of Web-Based Enterprise Management (WBEM). MACHINE/SYSTEM/CurrentControlSet/Enum	CREATOR OWNER SYSTEM	Full Control	
Control/Wmi/Security Security settings for the Windows Management Instrumentation (WMI). WMI is the Microsoft implementation of Web-Based Enterprise Management (WBEM). MACHINE/SYSTEM/CurrentControlSet/Enum Contains configuration data for hardware	CREATOR OWNER SYSTEM	Full Control	
Control/Wmi/Security Security settings for the Windows Management Instrumentation (WMI). WMI is the Microsoft implementation of Web-Based Enterprise Management (WBEM). MACHINE/SYSTEM/CurrentControlSet/Enum	CREATOR OWNER SYSTEM	Full Control	

REGISTRY KEY	USER GROUPS	RECOMMENDED	INHERIT
		PERMISSIONS	METHOD
\MACHINE\SYSTEM\CurrentControlSet\ Hardware Profiles	Administrators CREATOR OWNER	Full Control Full Control (Subkeys only)	Propagate
Contains system hardware profiles (changes to the initial hardware configuration stored in the Software and System keys).	SYSTEM Users	Full Control Read	
\MACHINE\SYSTEM\CurrentControlSet\ Services\SNMP\Parameters\ PermittedManagers	Administrators CREATOR OWNER SYSTEM	Full Control Full Control Full Control	Replace
Only exists if the SNMP service has been started on the system. The default permissions for this key allow Users to gather SNMP information that may in turn be used to attack the network.			
NOTE: These permissions are also set via a Windows 2000 post Service Pack 1 hotfix, <u>http://www.microsoft.com/</u> <u>windows2000/library/planni</u> <u>ng/security/secconfsteps.a</u> <u>Sp.</u> .			
\MACHINE\SYSTEM\CurrentControlSet\ Services\SNMP\Parameters\ ValidCommunities	Administrators CREATOR OWNER SYSTEM	Full Control Full Control Full Control	Replace
Only exists if the SNMP service has been started on the system. The default permissions for this key allow Users to gather SNMP information that may in turn be used to attack the network.			
NOTE: These permissions are also set via a Windows 2000 post Service Pack 1 hotfix, SNMP Parameters Vulnerability, KB Article Q266794 http://www.microsoft.com /technet/support/kb.asp?l D=266794.			
USERS\.DEFAULT	Administrators	Full Control	Replace
Profile that is used while the Windows 2000 CTRL+ALT+DEL logon message is displayed.	Users CREATOR OWNER SYSTEM	Read Full Control (Subkeys only) Full Control	
USERS\.DEFAULT\Software\Microsoft\ NetDDE	Administrators SYSTEM	Full Control Full Control	Replace
Settings for Network Dynamic Data Exchange, which is a protocol that allows applications to exchange data.			
USERSI.DEFAULT\Software\Microsoft\ Protected Storage Systems Provider	Ignore		Ignore
Used to protect user data. Inaccessible.			

Chapter 8 – Modifying Registry Security Settings with Security Templates

#### Table 13 Recommended Registry Permissions

This Page Intentionally Left Blank

Chapter

9

# Modifying File System Security Settings with Security Templates

NTFS is a secure file system that provides a reliable way to safeguard valuable information. NTFS works in concert with the Windows 2000 user account system to allow authenticated users access to files. The system provides extended permissions for controlling access to files and prohibits easy access to data on disk if someone manages to boot the system with another operating system. To implement the highest level of security, always format Windows 2000 partitions with the NT File System.

The security provided by NTFS is based on system controls that are managed by the Windows 2000 operating system. As long as Windows 2000 is operating, NTFS permissions and user access control lists prevent unauthorized users from accessing files either locally or over the network.

NTFS allows for varying levels of file access permissions to users or groups of users. Combined with file access permissions, is the concept of "inheritance." By default, newly created files or folders inherit the parent folder's file access permissions. Refer to the previous chapter on the registry for more information on Windows 2000 inheritance.

### File and folder permissions

To manually view permissions on a specific file or folder:

- □ In Windows Explorer, right-click on the file or folder
- □ Select Properties from the pull-down menu
- □ Click the Security tab
- Click Advanced to see more detailed permission information

File permissions may be set with more granularity than those listed in the Permissions dialog box by clicking the **Advanced** button. **Table 14** shows a list of granular file permissions. **Table 15** and **Table 16** show which granular permissions to select in order to achieve certain higher-level permissions for folders and files.

Special Permissions	Description
Traverse Folder/Execute File	<b>Traverse Folder</b> allows users to move through a folder to access other files or folders, regardless of permissions the user may or may not have on that folder (folders only). This permission only has meaning when the user has not been granted the <b>Bypass Traverse Checking</b> user right. The <b>Execute File</b> permission allows a user to run program files (files only).
List Folder/Read Data	List Folder allows the reading of file names and subfolders within a folder (folders only). Read Data allows file data to be read (files only).
Read Attributes	Allows viewing of a file's NTFS attributes (e.g.," Read only" or "Hidden").
Read Extended Attributes	Allows viewing of a file's extended attributes. Extended attributes may vary as they are defined by specific programs.
Create Files/Write Data	Create Files allows the creation of files within a folder (folders only). Write Data allows modification and/or overwriting of files (files only).
Create Folders/Append Data	<b>Create Folders</b> allows the creation of folders within a folder (folders only). <b>Append Data</b> allows making changes to the end of file (files only).
Write Attributes	Allows the modification of a file's NTFS attributes (e.g., "Read only" or "Hidden").
Write Extended Attributes	Allows the modification of a file's program-specific extended attributes.
Delete Subfolders and Files	Allows the deletion of subfolders and files regardless if the Delete permission was granted on the subfolder or file.
Delete	Allows deletion of a file or folder.
Read Permissions	Allows viewing of the permissions on a file or folder.
Change Permissions	Allows the modification of the permissions on a file or folder.
Take Ownership	Allows taking ownership of a file or folder.

**Table 14 File Permissions and Descriptions** 

### Folder Permissions:

Special Permissions	Full Control	Modify	Read & Execute	List Folder Contents	Read	Write
Traverse Folder/Execute File	X	X	X	X		
List Folder/Read Data	X	X	X	X	X	
Read Attributes	X	X	X	X	X	
Read Extended Attributes	X	X	X	X	X	
Create Files/Write Data	X	X				X
Create Folders/Append Data	X	X				X
Write Attributes	X	X				X
Write Extended Attributes	X	X				X
Delete Subfolders and Files	X					
Delete	X	X				
Read Permissions	X	X	x	X	X	X
Change Permissions	X					
Take Ownership	X					

# Chapter 9 – Modifying File System Security Settings with Security Templates

### **Table 15 Folder Permissions Options**



NOTE: List Folder Contents is inherited by folders but not files while Read and Execute is inherited by both folders and files.

### File Permissions:

Special Permissions	Full Control	Modify	Read & Execute	Read	Write
Traverse Folder/Execute File	X	X	X		
List Folder/Read Data	X	X	X	X	
Read Attributes	X	X	X	X	
Read Extended Attributes	X	X	X	X	
Create Files/Write Data	X	X			X
Create Folders/Append Data	X	X			X
Write Attributes	X	X			X
Write Extended Attributes	X	X			X
Delete Subfolders and Files	X				
Delete	X	X			
Read Permissions	X	X	X	X	X
Change Permissions	X				
Take Ownership	X				

### Table 16 File Permissions Options

### Modifying File System settings via the Security Template snap-in

The recommended changes to system files and folders are listed in Table 17.

The necessary changes can be made in one of two ways. The first method is to use the Security Configuration Tool Set to apply the recommended file and folder permissions. The alternative and more time-consuming method is to change permissions on each file and folder manually.

To view file system settings of a security template select the following in the MMC:

- □ Security Templates
- Default file directory (%SystemRoot%\Security\Templates)
- □ Specific configuration file
- □ File System

Modifying Permissions on a File or Folder

To modify the security settings on a particular file or folder already specified in the  $\inf$  file:

□ In the right frame, double-click on the file or folder to be changed

- □ Ensure that the **Configure this file or folder then** radio button is selected. Under this option, there are two other options:
  - Propagate inheritable permissions to all subfolders and files all subfolders and files that already inherit permissions from the folder being configured will inherit the new permissions. This option will have no affect on subfolders or files that do not have Allow inheritable permissions from parent to propagate to this object enabled in their DACLs
  - Replace existing permissions on all subfolders and files with inheritable permissions all subfolders and files will have their permissions set to the new permissions and will inherit from the key being configured regardless of any inheritance or blocking of inheritance on those subfolders or files
- □ Click Edit Security
- □ Ensure that the Allow inheritable permissions from parent to propagate to this object checkbox is unchecked
- □ Modify users and groups to reflect the recommended permissions by clicking the Add or Remove buttons
- □ For each user and/or group, set the permissions by clicking on the permission checkboxes
- □ The permissions that appear in the **Permissions** dialog box are Full Control, Modify, Read and Execute, List Folder Contents, Read, and Write. If these permissions are all that is desired and if the folder permissions encompass the folder itself and all subfolders and files below the key, click **Apply** → **OK**. Stop here

If extra granularity of permissions needs to be applied:

□ Click the Advanced button

NOTE: More granular permissions (special access) for a user and/or group can be configured through the Advanced dialog box.

- □ Click the user or group to be edited.
- Click View/Edit. A Permission Entry dialog box will appear.
- □ In the Apply onto pull-down menu, select the correct configuration (e.g., This folder only).
- $\Box \quad \text{Click } OK \to OK \to OK \to OK \text{ to exit}$

### Adding files or folders to the security configuration

To add a file or folder to the security configuration:

- □ Right-click on File System
- □ Select Add File from the pull-down menu
- □ Select the file or folder to be added
- Click OK
- □ A Configuration Security dialog box will appear

□ Configure the permissions according to the steps detailed in the previous **Modifying permissions on a file or folder** section

### Excluding files or folders from the security configuration

There are occasions when a specific file or folder should retain its current security settings. To ensure that parent folders do not propagate their new permissions down to such files or folders, the object may be excluded from configuration.

To exclude an object:

- □ In the right frame of File System, double-click on the file or folder to be changed
- **Click the Do not allow permissions on this file or folder to be replaced radio button**
- Click OK

### Recommended File and Folder Permissions

Folders and files not explicitly listed below are assumed to inherit the permissions of their parent folder. Folders with "Ignore" are explicitly excluded from security configuration and retain their original permissions. The term "Replace" indicates that the **Replace existing permissions on all subfolders and files with inheritable permissions** radio button should be enabled while "Propagate" indicates that the **Propagate inheritable permissions to all subfolders and files** radio button should be enabled. **Figure 6** shows these options. Unless otherwise noted, permissions are assumed to apply to all subfolders and files below the configured folder.



NOTE: Several of the security settings listed below are based on Microsoft's high security template (hisecws.inf). Microsoft chose to exclude several folders by setting the "Ignore" attribute in order to maintain the default security settings. However, it cannot be assumed that these default settings have not been modified in the past. Therefore, permissions have been set explicitly on most of these folders to reflect what the default permissions should be. In such cases, the "Propagate" option was selected.

In the domain controller security template, "W2K DC.inf," all instances of the **Users** group have been replaced with the **Authenticated Users** group.

Template Security Policy Setting	? ×
%SystemRoot%	
Configure this file or folder then	
C Propagate inheritable permissions to all subfolders and files	
<ul> <li><u>Replace existing permissions on all subfolders and files with</u> inheritable permissions</li> </ul>	
$\bigcirc$ $\underline{D}o$ not allow permissions on this file or folder to be replaced	
Edit Security	cel

### Figure 6 File/Folder Permission Inheritance Options

Folders and files in **Table 16** are alphabetized as they appear in the security templates GUI.

FOLDER OR FILE	USER GROUPS	RECOMMENDED	INHERIT
		PERMISSIONS	METHOD
<u>%ProgramFiles%</u>	Administrators CREATOR OWNER	Full Control Full Control	Replace
Folder in which applications are installed. By		(subfolders and files)	
default, this is %SystemDrive%\Program Files.	SYSTEM	Full Control	
	Users	Read, Execute	<b>D</b>
<u>%ProgramFiles%\Resource Kit</u> (servers and domain controllers)	Administrators SYSTEM	Full Control Full Control	Replace
<u>%ProgramFiles%\Resource Pro Kit</u>	OTOTEM		
(workstations)			
Folder where the Windows 2000 server Resource Kit (or professional resource kit) is			
installed.			
%SystemDirectory%	Administrators	Full Control	Replace
	CREATOR OWNER	Full Control	
Contains many operating system DLLs, drivers,	OVOTEM	(subfolders and files) Full Control	
and executable programs.	SYSTEM Users	Read, Execute	
%SystemDirectory%\appmgmt	Administrators	Full Control	Propagate
	SYSTEM	Full Control	
Contains application management files used for software installation.	Users	Read, Execute	
%SystemDirectory%\config	Administrators	Full Control	Replace
	SYSTEM	Full Control	-
Contains registry hive files.			<b>D</b> 1
%SystemDirectory%\dllcache	Administrators CREATOR OWNER	Full Control Full Control	Replace
Contains copies of protected system files.	SYSTEM	Full Control	
These copies are used by the System File			
Checker to repair corrupted or modified system			
files. %SystemDirectory%\DTCLog	Administrators	Full Control	Propagate
/// Jack Contraction of the Cont	CREATOR OWNER	Full Control	FTOpayate
Log file for MS Distributed Transaction		(subfolders and files)	
Coordinator, which is required for Microsoft	SYSTEM	Full Control	
Transaction Server. %SystemDirectory%\GroupPolicy	Users Administrators	Read, Execute	Dropogoto
<u>%SystemDirectory%GroupPolicy</u>	Authenticated Users	Read, Execute	Propagate
Folder containing local Group Policy Objects.	SYSTEM	Full Control	
%SystemDirectory%\ias	Administrators	Full Control	Replace
Contains databases for the Internet	CREATOR OWNER SYSTEM	Full Control Full Control	
Authentication Service.	STSTEIN		
%SystemDirectory%\Ntbackup.exe	Administrators	Full Control	Replace
	SYSTEM	Full Control	
File system backup program.	Administrators	Full Control	Dropogete
%SystemDirectory%\NTMSData	Administrators SYSTEM	Full Control Full Control	Propagate
Default location for the Removable Storage			
database.			<b></b>
%SystemDirectory%\rcp.exe	Administrators SYSTEM	Full Control Full Control	Replace
Remote copy command			
%SystemDirectory%\Regedt32.exe	Administrators	Full Control	Replace
	SYSTEM	Full Control	
Registry editing tool	Ignoro		lanoro
%SystemDirectory%\ReinstallBackups	Ignore		Ignore
Contains files used for reinstallations.			

FOLDER OR FILE	USER GROUPS	RECOMMENDED	INHERIT
FOLDER OR FILE	USER GROUPS	PERMISSIONS	METHOD
<u>%SystemDirectory%\repl</u>	Administrators SYSTEM	Full Control Full Control	Propagate
Folder containing scripts and files to be replicated or that have been replicated.	Users	Read, Execute	
%SystemDirectory%\repl\export	Administrators	Full Control	Propagate
	Replicator	Read, Execute	
Folder containing scripts and files to be	SYSTEM Users	Full Control	
replicated to other replication servers. %SystemDirectory%\repl\import	Administrators	Read, Execute	Propagate
<u>/////////////////////////////////////</u>	Replicator	Modify	FTOpagale
Folder containing scripts and files that have	SYSTEM	Full Control	
been replicated from other replication servers.	Users	Read, Execute	
%SystemDirectory%\rexec.exe	Administrators	Full Control	Replace
	SYSTEM	Full Control	
Program used to execute remote calls.			
%SystemDirectory%\rsh.exe	Administrators	Full Control	Replace
Brogrom used to evenute a remete shell	SYSTEM	Full Control	
Program used to execute a remote shell. %SystemDirectory%\secedit.exe	Administrators	Full Control	Replace
//////////////////////////////////////	SYSTEM	Full Control	Replace
Security configuration and analysis tool.	OTOTEM		
%SystemDirectory%\Setup	Administrators	Full Control	Propagate
	SYSTEM	Full Control	1 0
Contains setup DLLs.	Users	Read, Execute	
%SystemDirectory%\spool\Printers	Administrators	Full Control	Replace
	CREATOR OWNER	Full Control	
Printer spool.	SYSTEM	(subfolders and files) Full Control	
	Users	Traverse folder,	
	03613	Read attributes,	
		Read extended	
		attributes, Create	
		files, Create folders	
		(folder and	
		(folder and	
9/ Outom Drive 9/		subfolders)	Dranausta
<u>%SystemDrive%</u>	Administrators	subfolders) Full Control	Propagate
	Administrators CREATOR OWNER	subfolders) Full Control Full Control	Propagate
Drive on which Windows 2000 is installed.	CREATOR OWNER	subfolders) Full Control Full Control (subfolders and files)	Propagate
Drive on which Windows 2000 is installed. Contains important system startup and		subfolders) Full Control Full Control (subfolders and files) Full Control	Propagate
Drive on which Windows 2000 is installed. Contains important system startup and configuration files.	CREATOR OWNER SYSTEM	subfolders) Full Control Full Control (subfolders and files)	
Drive on which Windows 2000 is installed. Contains important system startup and	CREATOR OWNER SYSTEM Users Administrators SYSTEM	Subfolders) Full Control (subfolders and files) Full Control Read, Execute Full Control Full Control Full Control	Propagate Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u>	CREATOR OWNER SYSTEM Users Administrators	Subfolders) Full Control (subfolders and files) Full Control Read, Execute Full Control	
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u> Initialization file for DOS applications.	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users	Subfolders) Full Control (subfolders and files) Full Control Read, Execute Full Control Full Control Full Control Read, Execute	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b>	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators	Subfolders) Full Control (subfolders and files) Full Control Read, Execute Full Control Full Control Read, Execute Full Control Read, Execute	
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u> Initialization file for DOS applications.	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users	Subfolders) Full Control (subfolders and files) Full Control Read, Execute Full Control Full Control Full Control Read, Execute	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <u>c:\boot.ini</u> Boot menu.	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM	Subfolders) Full Control Full Control (subfolders and files) Full Control Full Control Full Control Read, Execute Full Control Full Control Full Control Full Control	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <u>c:\boot.ini</u> Boot menu. <b>%SystemDrive%\config.sys</b>	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM Administrators	Subfolders) Full Control Full Control (subfolders and files) Full Control Read, Execute Full Control Read, Execute Full Control Full Control Full Control Full Control Full Control	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <u>c:\autoexec.bat</u> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <u>c:\boot.ini</u> Boot menu.	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM Administrators SYSTEM	Subfolders) Full Control Full Control (subfolders and files) Full Control Read, Execute Full Control Read, Execute Full Control Full Control Full Control Full Control Full Control Full Control Full Control Full Control	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <b>c:\autoexec.bat</b> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <b>c:\boot.ini</b> Boot menu. <b>%SystemDrive%\config.sys</b> <b>c:\config.sys</b>	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM Administrators	Subfolders) Full Control Full Control (subfolders and files) Full Control Read, Execute Full Control Read, Execute Full Control Full Control Full Control Full Control Full Control	Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <u>c:\boot.ini</u> Boot menu. <b>%SystemDrive%\config.sys</b> <u>c:\config.sys</u> Initialization file for DOS applications.	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM Administrators SYSTEM Users	Subfolders) Full Control Full Control (subfolders and files) Full Control Read, Execute Full Control Read, Execute Full Control Full Control Full Control Full Control Full Control Read, Execute	Replace Replace Replace
Drive on which Windows 2000 is installed. Contains important system startup and configuration files. <b>%SystemDrive%\autoexec.bat</b> <b>c:\autoexec.bat</b> Initialization file for DOS applications. <b>%SystemDrive%\boot.ini</b> <b>c:\boot.ini</b> Boot menu. <b>%SystemDrive%\config.sys</b> <b>c:\config.sys</b>	CREATOR OWNER SYSTEM Users Administrators SYSTEM Users Administrators SYSTEM Administrators SYSTEM	Subfolders) Full Control Full Control (subfolders and files) Full Control Read, Execute Full Control Read, Execute Full Control Full Control Full Control Full Control Full Control Full Control Full Control Full Control	Replace

		RECOMMENDED	INHERIT
FOLDER OR FILE	USER GROUPS	PERMISSIONS	METHOD
%SystemDrive%\Documents and Settings\ Administrator	Administrators SYSTEM	Full Control Full Control	Replace
Folder containing the built-in Administrator profile.			
WARNING: There may be other administrator profiles on the system, such as local administrator profiles (for example, Administrator.localmachine name). Some of these profiles may inherit from its parent folder, Documents and Settings. To prevent these folders from inheriting the parent permissions (which give Users RX), add these folders into the security template and grant only Administrators and SYSTEM Full Control, removing the Users and/or Authenticated Users group from the ACL.			
%SystemDrive%\Documents and Settings\ All Users	Administrators SYSTEM Users	Full Control Full Control Read, Execute	Propagate
Folder containing desktop and profile attributes for all users.			
%SystemDrive%\Documents and Settings\ Default User	Administrators SYSTEM Users	Full Control Full Control Read, Execute	Replace
Folder containing default desktop and profile attributes for users logging on for the first time.			
<u>%SystemDrive%\Documents and Settings\</u> <u>All Users\Documents\DrWatson</u> Folder containing the Dr. Watson application error log.	Administrators CREATOR OWNER SYSTEM Users Users	Full Control Full Control (subfolders and files) Full Control Traverse folder, Create files, Create folders (subfolders and files) Read, Execute	Replace
%SystemDrive%\Documents and Settings\ All Users\Documents\DrWatson\ drwtsn32.log Dr. Watson application error log file.	Administrators CREATOR OWNER SYSTEM Users	Full Control Full Control Full Control Modify	Replace
SystemDrive%Inetpub (Servers only)	Ignore		Ignore
IIS web server folder. Only exists if IIS 5.0 is installed. Ignored in this document. See NSA's <i>Guide to the Secure Configuration and</i> <i>Administration of Microsoft Internet Information</i> <i>Services 5.0</i> for recommended file settings on this folder.			

	1	1	
FOLDER OR FILE	USER GROUPS	RECOMMENDED	INHERIT
		PERMISSIONS	METHOD
<u>%SystemDrive%\io.sys</u>	Administrators SYSTEM	Full Control Full Control	Replace
Initialization file for DOS applications.	Users	Read, Execute	
%SystemDrive%\msdos.sys	Administrators	Full Control	Replace
	SYSTEM	Full Control	
Initialization file for DOS applications.	Users	Read, Execute	
%SystemDrive%\My Download Files	Administrators	Full Control	Replace
	CREATOR OWNER	Full Control (subfolders and files)	
A default folder for downloaded documents.	SYSTEM	Full Control	
	Users	Read, Write,	
		Execute	
%SystemDrive%\ntdetect.com	Administrators	Full Control	Replace
<u>c:\ntdetect.com</u>	SYSTEM	Full Control	
Hardware detector during Windows 2000 boot.	Administratera	Full Control	Daplace
%SystemDrive%\ntldr c:\ntldr	Administrators SYSTEM	Full Control Full Control	Replace
	OTOTEM		
Windows 2000 operating system loader.			
%SystemDrive%\System Volume Information	Ignore		Ignore
Accessible only by SYSTEM.			
%SystemDrive%\Temp	Administrators	Full Control	Replace
Folder containing temporary files.	CREATOR OWNER	Full Control (subfolders and files)	
Folder containing temporary mes.	SYSTEM	Full Control	
	Users	Traverse folder,	
		Create files, Create	
		folders	
		(folders and	
%SystemRoot%	Administrators	subfolders) Full Control	Replace
	CREATOR OWNER	Full Control	
Folder in which the Windows 2000 operating		(subfolders and files)	
system is installed. By default, this is called	SYSTEM	Full Control	
winnt.	Users	Read, Execute	Depleci
<u>%SystemRoot%\\$NtServicePackUninstall\$</u>	Administrators SYSTEM	Full Control Full Control	Replace
Contains older versions of system files			
Contains older versions of system files necessary to back off a service pack.			
%SystemRoot%\\$NtUninstall* (all uninstall	Administrators	Full Control	Replace
folders)	SYSTEM	Full Control	
,			
Contains uninstall files for hotfixes and other			
applications.			
NOTE: Substitute the name			
of the folder(s) for \$NtUnininstall*. The			
security template will not			
recognize the wildcard			
character *.			
		1	

		RECOMMENDED	INHERIT
FOLDER OR FILE	USER GROUPS	PERMISSIONS	METHOD
%SystemRoot%\CSC	Administrators SYSTEM	Full Control Full Control	Replace
Contains all offline files requested by any user on the computer. CSC means "client side caching".			
%SystemRoot%\debug	Administrators	Full Control	Propagate
Containe vericus evetem and Active Directory	CREATOR OWNER	Full Control (subfolders and files)	
Contains various system and Active Directory logs.	SYSTEM	Full Control	
-	Users	Read, Execute	Description
%SystemRoot%\debug\UserMode	Administrators SYSTEM	Full Control Full Control	Propagate
Contains logs for group policy application to	Users	Traverse folder, List	
users.		folder, Create files	
	Users	(folder only) Create files, Create	
		folders	
		(files only)	
%SystemRoot%\NTDS	Administrators	Full Control	Propagate
(Domain Controllers only)	SYSTEM	Full Control	
Active Directory database folder.			
NOTE: The %SystemRoot% portion of the path name may need to be changed depending on where the default Active Directory folder Is located.			
%SystemRoot%\security	Administrators CREATOR OWNER	Full Control Full Control	Replace
Contains security templates and analysis	CREATOR OWNER	(subfolders and files)	
databases.	SYSTEM	Full Control	-
<u>%SystemRoot%\SYSVOL</u> (Domain Controllers only)	Administrators Authenticated Users	Full Control Read, Execute	Propagate
	CREATOR OWNER	Full Control	
Default Active Directory location for files that must be shared throughout a domain.	SYSTEM	(subfolders and files) Full Control	
NOTE: The %SystemRoot% portion of the path name may need to be changed depending on where the default Active Directory folder is located.			
%SystemRoot%\SYSVOL\domain\Policies	Administrators	Full Control	Propagate
(Domain Controllers only)	Authenticated Users CREATOR OWNER	Read, Execute Full Control	
Contains group policy objects.	Group Policy Creator	(subfolders and files) Modify	
NOTE: The %SystemRoot% portion of the path name may need to be changed depending on where the default Active Directory	Owners SYSTEM	Full Control	
folder is located.			

		RECOMMENDED	INHERIT
FOLDER OR FILE	USER GROUPS	PERMISSIONS	METHOD
%SystemRoot%\Offline Web Pages	Ignore		Ignore
Folder containing web pages that have been downloaded for off-line viewing.			
%SystemRoot%\regedit.exe Registry editing tool.	Administrators SYSTEM	Full Control Full Control	Replace
<b>SystemRoot%Registration</b> Folder containing Component Load Balancing (CLB) registration files read by COM+ applications.	Administrators SYSTEM Users	Full Control Full Control Read	Propagate
%SystemRoot%\repair Backup files of SAM database and other important registry and system files to be used during a system repair.	Administrators SYSTEM	Full Control Full Control	Replace
%SystemRoot%\Tasks Folder containing jobs scheduled by Task Scheduler.	Ignore		Ignore
<u>%SystemRoot%\Temp</u> Folder containing temporary files.	Administrators CREATOR OWNER SYSTEM Users	Full Control Full Control (subfolders and files) Full Control Traverse folder, Create files, Create folders (folders and subfolders)	Replace

		RECOMMENDED	INHERIT
FOLDER OR FILE	USER GROUPS	PERMISSIONS	METHOD
<u>C:\ntbootdd.sys</u>	Administrators SYSTEM	Full Control Full Control	Replace
Copy of the SCSI device driver. Used when using SCSI or Signature syntax in boot.ini.			

**Table 17 Recommended File Permissions** 

Chapter

10

# Security Configuration and Analysis

Once the appropriate security templates have been modified, security analysis and configuration can be performed via the Security Configuration and Analysis snap-in or command line operations. This procedure should be conducted when applying a security configuration to a local system. For instructions on importing security templates into Group Policy, see the *Guide to Securing Microsoft Windows 2000 Group Policy*.



WARNING: Applying a secure configuration to a Windows 2000 system may result in a loss of performance and functionality.

### Loading the Security Configuration and Analysis snap-in into the MMC

To load the Security Configuration and Analysis snap-in into the MMC:

- Run the Microsoft Management Console (mmc.exe)
- □ Select Console → Add/Remove Snap-in
- □ Click Add
- □ Select Security Configuration and Analysis
- □ Click Add
- □ Click Close
- □ Click OK

To avoid having to reload the snap-in every time the MMC is exited and reopened, save the current console settings by performing the following:

- □ In the Console menu, select Save. By default, the file will be saved in the Administrative Tools menu of the currently logged-on user.
- Enter the file name under which the current console settings will be saved

From then on, the console can be accessed from Start  $\rightarrow$  Program Files  $\rightarrow$  Administrative Tools.



NOTE: More than one snap-in can be loaded into the MMC at one time. E.g., the Security Templates and Security Configuration and Analysis templates can both be loaded into a console that is saved for future use.

### Security Configuration Databases

The Security Configuration and Analysis snap-in uses a database to store settings for an analysis or configuration. To open an existing database or new database while using the GUI:

- □ In the MMC, right click on the Security Configuration and Analysis node
- □ Select Open Database
- □ Enter the name of an existing database or a new database
- □ Click Open



NOTE: It is recommended that a new database be created for each analysis and configuration coupling.

Configuration files may be imported into the database by executing the following procedure:

- □ If a new database name was entered when opening a database, user will automatically be prompted to enter the configuration file to import. Otherwise:
- Right click on the Security Configuration and Analysis node in the left pane of the MMC
- □ Select Import Template
- □ In the Import Template dialog box, select the appropriate inf configuration file.
- □ Check the Clear this database before importing box to remove any previous settings stored in the database as illustrated in Figure 7.



NOTE: Import operations can append to or overwrite database information that has been previously imported. Appending is the default. If user does not want to combine templates in a configuration, check the "Clear this database before importing" checkbox to overwrite the current database.



WARNING: To avoid confusion and accidental combining of configurations, it is recommended that this option be checked every time a new analysis or configuration is performed.

□ Click Open

Import 1	ſempla	ite					? ×
Look jn:	🔂 t	emplates		•	← 🗈	d 🔁	]+
👼 hised	dc.inf		5	securews.inf			
	ws.inf		3	setup security	.inf		
	sid.inf		5	W2K DC.inf			
	ss.inf		5	W2K Domain P	olicy Temp	late.inf	
🐻 ocfile	sw.inf		5	W2K Server.in	F		Type: Setu
🛛 🗟 secu	redc.inf		3	W2K Workstat	ion.inf		Size: 26.5
•							F
File <u>n</u> am	e: [	W2K DC.inf				<u>0</u>	pen
Files of <u>t</u>	ype:	Security Template	(.inf)		•	Ca	incel
<b>▼</b> <u>C</u> lea	ar this da	atabase before imp	orting				//.

Figure 7 Configuration File Selection

### Secedit Command Line Options

Secedit.exe, introduced in Chapter 1, is useful for performing security analyses and configurations via the command line and batch and/or scheduled programs. The command line syntax for secedit when used for system analysis or configuration is:

secedit {/analyze | /configure} [/cfg filename] [/db filename] [/log LogPath] [/verbose] [/quiet] [/overwrite] [/areas Areas]

Parameter	Description	
/analyze	Performs an analysis	
/configure	Performs a configuration	
/cfg filename	Path to a configuration file that will be appended to the database prior to performing the analysis	
/db filename	Path to the database that secedit will perform the analysis against. If this parameter is not specified, the last configuration/analysis database is used. If there is no previous database, %SystemRoot%\Security\Database\secedit.sdb is used. <b>NOTE:</b> It is recommended that a new database be created for each analysis and configuration coupling.	
/log LogPath	Path to log file for the process. If not provided, progress information is output to the console. NOTE: Log information is appended to the specified log file. User must specify a new file name if a new log file is to be created.	
/verbose	Specify detailed progress information	

**Table 18** explains the parameter syntax for secedit.exe options.

Parameter	Description	
/quiet	Suppress screen and log output	
/overwrite	Overwrite the named database with the given configuration information. NOTE: Configuration files can be appended to or overwrite database information that has been previously created. Appending is the default. Specify the /overwrite option to overwrite the current database. WARNING: To avoid confusion and accidental combining of configurations, it is recommended that this option be included every time a new analysis or configuration is performed.	
/areas Areas	Only relevant when using the /configure switch. Specifies the security areas to be processed. The following areas are available: SECURITYPOLICY - Local policy and domain policy for the system, including account policies, audit policies, etc. GROUP_MGMT - Restricted Group settings USER_RIGHTS - User rights assignments DSOBJECTS - Security on directory objects REGKEYS - Security permissions on local registry keys FILESTORE - Security permissions on local file system SERVICES - Security configuration for all defined services NOTE: If the /areas switch is not used, the default is all security areas. If used, each area name should be separated by a space.	

### **Table 18 Secedit Command Line Parameters**

Secedit has several other options available as well. These are detailed in

Parameter	Description
/export	Exports a stored template from a security database to a security template file
/refreshpolicy {machine_policy   user_policy} {/enforce}	Refreshes system security by reapplying the security settings to the Group Policy object (or Local Group Policy Object). The parameters available with this option are:
	<i>machine_policy</i> – reapply machine-related settings; this option will be most used for security settings since the recommended settings are machine-specific
	user_policy – reapply user-related settings
	/enforce - reapply settings regardless of whether they have changed
/validate <filename></filename>	Validates the syntax of a template to be imported into a database for analysis or configuration

### Performing a Security Analysis

A security analysis is performed against a database. The configuration file(s) that have been imported into the database define the *baseline* for the analysis. Security settings within the configuration file(s) are compared to the current system security settings, and the results are stored back into a database. The baseline settings are presented alongside the current system settings. Configuration information can be modified as a

result of the analysis. The modified configuration information can be exported into a configuration file for subsequent use.

Performing a Security Analysis via the Command Line

To perform a security analysis via the command line, execute the following in a CMD prompt window:

secedit /analyze [/cfg filename] [/db filename] [/log LogPath] [/verbose] [/quiet] [/overwrite] [>> results\_file]

*results\_file* is the name of a file to contain the analysis results. This is especially useful for reviewing the results at a later time. If the >> *results\_file* is omitted, output will be written to the screen.

### Performing a Security Analysis via the GUI

**Figure 8** shows a sample result of a security analysis via the Security Configuration and Analysis snap-in. The following steps should be followed to perform a security analysis via the GUI:

- □ Right-click on the **Database** node
- □ Select Analyze Computer Now...
- □ In the Perform Analysis dialog box, enter the error log file path.



NOTE: Log information is appended to the specified log file. A new file name must be specified if a new log file is to be created.

Click OK

áction Yiew Eavontes 🏻 💠 🔿 🖪	m 18 19		
ce   Pavertes	Taky A	Database Setting	Computer Setting
	Additional restrictions for anonymous connections		None, Rely on defa
Console Rost	T Alixy server operators to schedule tasks (domain controllers only)	hat defined	Disabled
Security Templates	Allow mystem to be shut down without having to log an	Deabled	Enabled
B ( C/WINNT/Security/Templates Security Configuration and Analysis	22/allowed to eject removable NTFS media	Administrators	Administrations
Account Policies	A present of the time required before deconnecting session	30 minutes	15 minutes
- Password Polcy	Mudit the access of global cystem objects	Ecubled	Dicabled
Account Ladeut Palicy	Added use of Badrup and Restore privilege	Enabled	Deabled
E B Local Policies	22/Jutomatically log off users when logon time expires (local)	Enabled	Enabled
B Audt Policy	Clear vitual memory pagefile when system shuts down	Evobled	Deabled
E User Rights Assignment	22Digitally sign client canaxunication (always)	Disabled	Disabled
E Security Options	Digitally sign client communication (when possible)	Evabled	Evabled
8 B Event Log	22Digitally sign server communication (when personer)	Disabled	Disabled
8- 💁 Restricted Groups	Totataly sign server communication (when possible)	Evabled	Disabled
8- 🥶 System Services	22Disable CTRL+ALT+DEL requirement for logon	Disabled	Disabled
8 📑 Registry	to not display last user name in logon screen	Evabled	Disabled
🖹 🎲 File System	CAN Manager Authentication Lavel	an rowing to	Send LM & MTLM re
	Message text for users attempting to log on	* Entw Lagon Barn	SHELLPH GEN IGPLINE
	The manager table for users attempting to log on	* enter Logon Ness	
	Thumber of previous logans to cache (in case domain controller is not available)	Billingens	t0 logons
	Provent system maintenance of computer account password	Disabled	Disabled
	Prevent users from instaling printer drowns	Evabled	Disabled
	Prove a core for incoming parate carriers	14 days	L4 days
	Recovery Console: Allow automatic administrative logon	Disabled	Disabled
	Recovery Console: Allow Rogov copy and access to all drives and all folders	Deabled	Disabled
	Rename administratory account	ADMINISTRATOR	vAOPENESTRATOR
	Prevame quest account	RUEST	VO.FST
	Restrict CD-ROM access to locally logged-on user only	Enabled	Disabled
	Theshird Co-Horn access to locally logged-on user only	Evabled	Disabled
	22Secure channel: Digitally encryst or sign secure channel data (always)	Disabled	Disabled
	22Secure channel: Digitally encryst secure channel data (when possible)	Evabled	Enabled
	23Secure channel: Digitally sign secure channel data (when possible)	Enabled	Enabled
	23 Secure channel: Require strong (Windows 2000 or later) session key	Disabled	Dicabled
	Send unencrypted password to connect to third-party 546 servers	Deabled	Disabled
	Shut down system immediately if unable to log security audits	Evabled	Disabled
	Construct down system innediately if unable to tog security audits	Lock Warkstein	Na Action
	Strengthen default permissions of global system objects (e.g. Symbolic Links)	Lock Warkstotton	Re Action Enabled
	Sooreingthen denaut permissions ar global system objects (e.g. symbolic Lines)     P3 transmid denaut permissions halvastee	Manual in A allow and	Man hat allowing

Figure 8 Results of a Security Analysis

### Configuring a System

During configuration, errors may result if specific files or registry keys do not exist on the system, but exist in the inf configuration file. Do not be alarmed. The inf files attempt to cover many different scenarios and configurations that your system may or may not match.

### Configuring a System via the Command Line

To configure all of the available security options at one time via the command line:

secedit /configure [/cfg filename] [/db filename] [/log LogPath] [/verbose] [/quiet] [/overwrite] [/areas Areas]

WARNING: Failure to enter a new database name each time a configuration is made or specify the /overwrite option may result in unpredictable behavior by secedit. For example, imported configuration files could get merged with other files and report unexpected analyses.

Following is an example of using the command line tool to configure only specific security areas:

secedit /configure /cfg "W2K workstation.inf" /db newdb.sdb /log logfile.txt /overwrite /areas REGKEYS FILESTORE This example will import the "W2K workstation.inf" file system and registry permission security settings and configure the local system.

### Configuring a System via the GUI

The following steps should be followed to configure a system using the Security Configuration and Analysis snap-in:

- □ Right-click on the Database node
- □ Select Configure Computer Now....
- □ In the Configure System dialog box, enter the error log file path.



NOTE: Log information is appended to the specified log file. A new file name must be specified if a new log file is to be created.

□ Click OK

|--|

NOTE: When a system is configured via the GUI, all settings in the template are applied. There is no option, as with secedit.exe, to specify that only parts of the template, e.g. file permissions or account policies, are to be applied.

This Page Intentionally Left Blank

Appendix

# **Example Logon Banner**

The DoD uses a standard warning banner that can be downloaded from the United States Navy INFOSEC Web Information Service <u>http://infosec.nosc.mil/infosec.html</u>. Select the text under the United States Department of Defense Warning Statement and copy it to the clipboard. This banner should resemble the following message:

"This is a Department of Defense computer system. This computer system, including all related equipment, networks, and network devices (specifically including Internet access), is provided only for authorized U. S. Government use. DoD computer systems may be monitored for all lawful purposes, including to ensure that their use is authorized, for management of the system, to facilitate protection against unauthorized access, and to verify security procedures, survivability, and operational security. Monitoring includes active attacks by authorized DoD entities to test or verify the security of this system. During monitoring, information may be examined, recorded, copied, and used for authorized purposes. All information, including personal information, placed on or sent over this system may be monitored. Use of this DoD computer system, authorized or unauthorized, constitutes consent to monitoring of this system. Unauthorized use may subject you to criminal prosecution. Evidence of unauthorized use collected during monitoring may be used for administrative, criminal or adverse action. Use of this system constitutes consent to monitoring for these purposes."

Windows 2000 displays a message box with a caption and text that can be configured before a user logs on to the machine. The DoD requires organizations to use this message box to display a warning that notifies users that they can be held legally liable if they attempt to log on without authorization to use the computer. The absence of such a notice could be construed as an invitation, without restriction, to log on to the machine and browse the system.

# Appendix

# References

- Ackerman, Pilar, et. al., *Microsoft Windows 2000 Professional Resource Kit*, Redmond, Washington: Microsoft Press, 2000.
- Bartock, Paul, Julie Haney, et. al., *Guide to Securing Microsoft Windows NT Networks version* 4.1, National Security Agency, September 2000.
- "Default Access Control Settings in Windows 2000," <u>http://www.microsoft.com/windows2000/techinfo/planning/security/secdefs.asp</u>, Microsoft white paper, 2000.
- "Event ID 1000 and 1202 After Configuring Policies," KB article Q260715 <u>http://support.microsoft.com/support/kb/articles/Q260/7/15.asp</u>, Microsoft, 2000.
- "How to Use the RestrictAnonymous Registry Value in Windows 2000," KB article Q246261 <u>http://support.microsoft.com/support/kb/articles/Q246/2/61.asp</u>, Microsoft, 2000.
- McLean, Ian, *Windows 2000 Security Little Black Book*, Scottsdale, Arizona: Coriolis Group, 2000.

Microsoft Technet, <u>http://www.microsoft.com/technet</u>.

- "OFF2000: 'Installation Ended Prematurely Because of an Error' When You Run Office Setup," KB article Q230895 <u>http://support.microsoft.com/support/kb/articles/Q230/8/95.asp</u>, Microsoft, 2000
- Russel, Charlie and Sharon Crawford, *Microsoft Windows 2000 Server Administrator's Companion*, Redmond, Washington: Microsoft Press, 2000.

"Security Configuration Toolset," <u>http://www.microsoft.com/windows2000/techinfo/howitworks/security/sctoolset.asp,</u> Microsoft white paper, 2000.

Smith, Randy Franklin, "Dangerous Services," Windows IT Security web site,

http://www.windowsitsecurity.com/Articles/Index.cfm?ArticleID=16301, Dec. 7, 2000.

"SNMP Parameters Vulnerability," KB article Q266794

<u>http://www.microsoft.com/technet/support/kb.asp?ID=266794</u>, Microsoft, December 2000.

"Step-by-Step Guide to Using the Security Configuration Tool Set,"

http://www.microsoft.com/windows2000/library/planning/security/secconfsteps.asp, Microsoft, February 2000